Object Storage Service

Android SDK Developer Guide

Issue	01
Date	2025-05-16

HUAWEI TECHNOLOGIES CO., LTD.

Copyright © Huawei Technologies Co., Ltd. 2025. All rights reserved.

No part of this document may be reproduced or transmitted in any form or by any means without prior written consent of Huawei Technologies Co., Ltd.

Trademarks and Permissions

and other Huawei trademarks are trademarks of Huawei Technologies Co., Ltd.
All other trademarks and trade names mentioned in this document are the property of their respective holders.

Notice

The purchased products, services and features are stipulated by the contract made between Huawei and the customer. All or part of the products, services and features described in this document may not be within the purchase scope or the usage scope. Unless otherwise specified in the contract, all statements, information, and recommendations in this document are provided "AS IS" without warranties, guarantees or representations of any kind, either express or implied.

The information in this document is subject to change without notice. Every effort has been made in the preparation of this document to ensure accuracy of the contents, but all statements, information, and recommendations in this document do not constitute a warranty of any kind, express or implied.

Security Declaration

Vulnerability

Huawei's regulations on product vulnerability management are subject to the *Vul. Response Process.* For details about this process, visit the following web page:
https://www.huawei.com/en/psirt/vul-response-process
For vulnerability information, enterprise customers can visit the following web page:
https://securitybulletin.huawei.com/enterprise/en/security-advisory

Contents

1 Installing the SDK....1
2 Example Programs....2
3 Quick Start....4
3.1 Before You Start....4
3.2 Setting Up an OBS Environment....4
3.3 Preparing a Development Environment....6
3.4 Installing the SDK....6
3.5 Obtaining Endpoints....7
3.6 Initializing an Instance of ObsClient....7
3.7 Creating a Bucket....8
3.8 Uploading an Object....9
3.9 Downloading an Object....9
3.10 Listing Objects....10
3.11 Deleting an Object....10
3.12 General Examples of ObsClient....11
4 Initialization....13
4.1 Configuring the AK/SK....13
4.2 Creating an Instance of ObsClient....13
4.3 Configuring an Instance of ObsClient....15
4.4 Configuring SDK Logging....20
5 Bucket Management....21
5.1 Creating a Bucket....21
5.2 Listing Buckets....23
5.3 Deleting a Bucket....24
5.4 Identifying Whether a Bucket Exists....24
5.5 Obtaining Bucket Metadata....25
5.6 Managing Bucket ACLs....25
5.7 Managing Bucket Policies....30
5.8 Obtaining a Bucket Location....31
5.9 Obtaining Storage Information About a Bucket....32
5.10 Setting or Obtaining a Bucket Quota....32
5.11 Storage Class....33

 Copyright © Huawei Technologies Co., Ltd.

6 Object Upload 36
6.1 Object Upload Overview 36
6.2 Performing a Streaming Upload 37
6.3 Performing a File-Based Upload 38
6.4 Obtaining Upload Progresses 39
6.5 Creating a Folder 40
6.6 Setting Object Properties 41
6.7 Performing a Multipart Upload 44
6.8 Configuring Lifecycle Management 53
6.9 Performing an Appendable Upload 54
6.10 Performing a Multipart Copy 55
6.11 Performing a Resumable Upload 57
6.12 Performing a Browser-Based Upload 60
7 Object Download 63
7.1 Object Download Overview 63
7.2 Performing a Streaming Download 63
7.3 Performing a Partial Download 64
7.4 Obtaining Download Progresses 65
7.5 Performing a Conditioned Download 66
7.6 Rewriting Response Headers 68
7.7 Obtaining Customized Metadata 69
7.8 Downloading an Archive Object 70
7.9 Performing a Resumable Download 71
7.10 Processing an Image 74
8 Object Management 75
8.1 Setting Object Properties 75
8.2 Obtaining Object Attributes 76
8.3 Managing Object ACLs 76
8.4 Listing Objects 78
8.5 Deleting Objects 83
8.6 Copying an Object 84
9 Temporarily Authorized Access 88
9.1 Using a Temporary URL for Authorized Access 88
10 Versioning Management 96
10.1 Versioning Overview 96
10.2 Setting Versioning Status for a Bucket 96
10.3 Viewing Versioning Status of a Bucket 98
10.4 Obtaining a Versioning Object 99
10.5 Copying a Versioning Object 99
10.6 Restoring a Specific Archive Object Version 100
10.7 Listing Versioning Objects 101

 Copyright © Huawei Technologies Co., Ltd.

10.8 Object Version ACL 105
10.9 Deleting Versioning Objects 106
11 Lifecycle Management 108
11.1 Lifecycle Management Overview 108
11.2 Setting Lifecycle Rules 109
11.3 Viewing Lifecycle Rules 110
11.4 Deleting Lifecycle Rules 111
12 CORS 113
12.1 CORS Overview 113
12.2 Setting CORS Rules 113
12.3 Viewing CORS Rules 115
12.4 Deleting CORS Rules 115
13 Access Logging 117
13.1 Logging Overview 117
13.2 Enabling Bucket Logging 117
13.3 Viewing Bucket Logging 119
13.4 Disabling Bucket Logging 119
14 Static Website Hosting 121
14.1 Static Website Hosting Overview 121
14.2 Website File Hosting 121
14.3 Setting Website Hosting 122
14.4 Viewing Website Hosting Settings 124
14.5 Deleting Website Hosting Settings 125
15 Tag Management 126
15.1 Tagging Overview 126
15.2 Setting Bucket Tags 126
15.3 Viewing Bucket Tags 127
15.4 Deleting Bucket Tags 127
16 Server-Side Encryption 129
16.1 Server-Side Encryption Overview 129
16.2 Encryption Description 129
16.3 Example of Encryption 130
17 Troubleshooting 132
17.1 OBS Server-Side Error Codes 132
17.2 SDK Custom Exceptions 140
17.3 SDK Common Response Headers 140
17.4 Log Analysis 140
17.5 Lack of Classes 142
17.6 Connection Timeout 142
17.7 Resources Cannot Be Released 142

 Copyright © Huawei Technologies Co., Ltd.

17.8 Unmatched Signatures 142
17.9 NetworkOnMainThreadException 143
18 FAQ 144
18.1 Does the SDK Support Uploading, Downloading, or Copying Objects in a Batch? 144
A API Reference 146

 Copyright © Huawei Technologies Co., Ltd.

1 Installing the SDK

Download Address

- Latest version of OBS Android SDK: **OBS Android SDK**

Source Code and API Reference

- For details about the SDK source codes, see **GitHub**.
- For the API documentation, see **OBS SDK for Android API**.

Compatibility

- For details about the version revision records, see **ChangeLog**.
- Recommended Android versions: Android 7.0, 8.0, 8.1, 9.0, and 10.0 (HTTP/HTTPS)
- If you are using the JDK 1.8 environment, version 3.21.12 is recommended for OBS Android SDK.
- Namespace: Compatible with earlier versions (2.1.*x*). All external APIs are contained in the **com.obs.services**, **com.obs.services.model**, and **com.obs.services.exception** packages.
- API functions: Compatible with earlier versions (2.1.*x*).

  NOTE

  If Android 4.4 or an earlier version is used, configure HTTP to access OBS.

ProGuard

```
#okhttp
-dontwarn okhttp3.**
-keep class okhttp3.**{*;}

#okio
-dontwarn okio.**
-keep class okio.**{*;}

#sdk
-keep class com.obs.services.** {*;}
-keep class com.obs.log.** {*;}

#java-xmlbuilder
-keep class com.jamesmurty.utils.**{*;}
```

 Copyright © Huawei Technologies Co., Ltd.

2 Example Programs

OBS Android SDK provides abundant example programs for user reference and direct use. These programs can be obtained from the OBS Android SDK development package. For example, files in **eSDK_Storage_OBS_*<versionId>*_Android/samples_android** obtained by decompressing **eSDK_Storage_OBS_*<versionId>*_Android.zip** are example programs. Alternatively, you can click code package names provided in the following table to obtain corresponding example programs.

Example programs include:

Sample Code	Description
BucketOperationsSample	How to use bucket-related APIs.
ObjectOperationsSample	How to use object-related APIs.
DownloadSample	How to download an object.
CreateFolderSample	How to create a folder.
DeleteObjectsSample	How to delete objects in a batch.
ListObjectsSample	How to list objects.
ListVersionsSample	How to list versioning objects.
ListObjectsInFolderSample	How to list objects in a folder.
ObjectMetaSample	How to customize object metadata.
SimpleMultipartUploadSample	How to perform a multipart upload.
ConcurrentCopyPartSample	How to concurrently copy parts of a large object.
ConcurrentDownloadObjectSample	How to concurrently download parts of a large object.
ConcurrentUploadPartSample	How to concurrently upload parts of a large object.

 Copyright © Huawei Technologies Co., Ltd.

Sample Code	Description
RestoreObjectSample	How to download Archive objects.
PostObjectSample	How to perform a browser-based upload.
TemporarySignatureSample	How to use URLs for authorized access.

Copyright © Huawei Technologies Co., Ltd.

3 Quick Start

3.1 Before You Start

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

- Ensure that you are familiar with OBS basic concepts, such as **buckets**, **objects**, and **access keys (AK and SK)**.
- You can see **General Examples of ObsClient** to learn how to call OBS Android SDK APIs in a general manner.
- After an API is called using an instance of **ObsClient**, if no exception is thrown, the return value is valid. If an exception is thrown, the operation fails. For details about errors, see **SDK Custom Exceptions**.
- After an API is successfully called by an instance of **ObsClient**, an instance of **HeaderResponse** (or of its sub-class) containing the response headers will be returned.
- Some features are available only for some regions. If **405** HTTP status code is returned for a certain feature API, check whether the region supports that feature.

3.2 Setting Up an OBS Environment

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

 Copyright © Huawei Technologies Co., Ltd.

Step 1 Sign up for a cloud service account.

Create an account to use OBS. If you already have one, use it instead.

1. Open a browser.
2. Visit the **Huawei Cloud official website**.
3. In the upper right corner of the page, click **Register**.
4. Enter the registration information and click **Register**.

Step 2 Subscribe to OBS.

Ensure that your account balance is sufficient before using OBS.

1. Log in to OBS Console.
2. In the upper right corner, click **Billing & Costs**. In the navigation pane of the displayed page, choose **Funds Management**.
3. Click **Top Up**. The dialog box for top-up is displayed.
4. Top up the account as prompted.
5. After the top-up is successful, close the window and go back to the homepage of the management console.
6. Click **Object Storage Service** to subscribe to OBS and enter OBS Console.

Step 3 Create access keys.

OBS uses the AK and SK in a user account for signature verification to make sure that only authorized accounts can access specified OBS resources. Detailed explanations about AK and SK are as follows:

- An access key ID (AK) defines a user who accesses the OBS system. An AK belongs to only one user, but one user can have multiple AKs. The OBS system recognizes the users who access the system by their access key IDs.
- An SK is the secret access key on OBS, which is required as the key to access OBS. You can generate authentication information based on SKs and request header fields. An SK matches an AK, and they group into a pair.

The procedure is as follows:

1. Log in to OBS Console.
2. In the upper right corner of the page, hover the cursor over the username and choose **My Credentials**.
3. On the **My Credentials** page, select **Access Keys** in the navigation pane on the left.
4. On the **Access Keys** page, click **Create Access Key**.
5. In the **Create Access Key** dialog box that is displayed, enter the password and verification code.

   NOTE

   - If you have not bound an email address or mobile number, enter only the password.
   - If you have bound an email address and a mobile number, you can select the verification by either email or mobile phone.
6. Click **OK**.

 Copyright © Huawei Technologies Co., Ltd.

7. In the **Download Access Key** dialog box that is displayed, click **OK** to save the access keys to your browser's default download path.
8. Open the downloaded **credentials.csv** file to obtain the access keys (AK and SK).

NOTE

- Each user can create up to two valid AK/SK pairs.
- To prevent the AK/SK from being leaked, keep them secure. If you click **Cancel** in the dialog box, the access keys will not be downloaded, and cannot be obtained later. You can re-create access keys if you need to use them.

----End

3.3 Preparing a Development Environment

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

- Download Android Studio of the latest version from the **Android Studio's official website** and install it.
- After installation, on Android Studio, choose **Settings** > **Appearance & Behavior** > **System Settings** > **Android SDK** to install SDK platforms for supporting application programs, for example, Android 5.0 (Lollipop).

3.4 Installing the SDK

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Use the Gradle of Android Studio to download and install the OBS Android SDK. The procedure is as follows:

Step 1 Open Android Studio. Click **Start a new Android Studio project** to go to the page for creating a project.

Step 2 Fill in the configuration items, such as **Application name** and **Project location**, and finish creating the project as prompted.

Step 3 In Android Studio, find the **build.gradle** file (not the one in the **app** folder) in the root directory of the new project and add the following information to the file:

```
repositories{
    maven {
```

 Copyright © Huawei Technologies Co., Ltd.

```
        url 'https://mirrors.huaweicloud.com/repository/maven/'
    }
    mavenCentral()
}
```

Step 4 Find the dependencies node from the **build.gradle** file in the **app** folder of the new project and add a line to the node. as follows:

```
implementation 'com.huaweicloud:esdk-obs-android:3.24.3'
```

Step 5 Open the **AndroidManifest.xml** file and add the following code segments to configure the SDK-required permissions:

```
<uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.READ_EXTERNAL_STORAGE" />
<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />
<uses-permission android:name="android.permission.ACCESS_NETWORK_STATE" />
<uses-permission android:name="android.permission.ACCESS_WIFI_STATE" />
<uses-permission android:name="android.permission.GET_TOP_ACTIVITY_INFO" />
```

Step 6 Compile the project and download the SDK using the gradle to complete the integration.

----End

3.5 Obtaining Endpoints

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

- You can click **here** to view the endpoints and regions enabled for OBS.

NOTICE

The SDK allows you to pass endpoints with or without the protocol name. Suppose the endpoint you obtained is **your-endpoint**. The endpoint passed when initializing an instance of **ObsClient** can be **http://your-endpoint**, **https://your-endpoint**, or **your-endpoint**.

3.6 Initializing an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

 Copyright © Huawei Technologies Co., Ltd.

Each time you want to send an HTTP/HTTPS request to OBS, you must create an instance of **ObsClient**. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Use the instance to access OBS.

// Close obsClient.
obsClient.close();
```

NOTE

For more information, see chapter "Initialization."

For details about logging configuration, see **Configuring SDK Logging**.

3.7 Creating a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

A bucket is a global namespace of OBS and is a data container. It functions as a root directory of a file system and can store objects. The following code shows how to create a bucket:

```
obsClient.createBucket("bucketname");
```

NOTE

- Bucket names are globally unique. Ensure that the bucket you create is named differently from any other bucket.
- A bucket name must comply with the following rules:
  - Contains 3 to 63 characters, chosen from lowercase letters, digits, hyphens (-), and periods (.), and starts with a digit or letter.
  - Cannot be an IP address or similar.
  - Cannot start or end with a hyphen (-) or period (.)
  - Cannot contain two consecutive periods (.), for example, **my..bucket**.
  - Cannot contain periods (.) and hyphens (-) adjacent to each other, for example, **my-.bucket** or **my.-bucket**.
- If you create buckets of the same name, no error will be reported and the bucket properties comply with those set in the first creation request.
- For more information, see **Creating a Bucket**.

 Copyright © Huawei Technologies Co., Ltd.

NOTICE

- During bucket creation, if the endpoint you use corresponds to the default region CN North-Beijing1 (cn-north-1), specifying a region is not a must. If the endpoint you use corresponds to any other region, except the default one, you must set the region to the one that the used endpoint corresponds to. For more information about the valid regions, see **Regions and Endpoints**.
- You can specify a region for a bucket during bucket creation. For details, see **Creating a Bucket with Parameters Specified**.

3.8 Uploading an Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

This example uploads string **Hello OBS** to bucket **bucketname** as object **objectname**.

The example code is as follows:

```
obsClient.putObject("bucketname", "objectname", new ByteArrayInputStream("Hello OBS".getBytes()));
```

NOTE

- For more information, see **Object Upload Overview**.

3.9 Downloading an Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

This example downloads object **objectname** from bucket **bucketname**.

The example code is as follows:

```
ObsObject obsObject = obsClient.getObject("bucketname", "objectname");
InputStream content = obsObject.getObjectContent();
if (content != null)
{
    BufferedReader reader = new BufferedReader(new InputStreamReader(content));
    while (true)
    {
        String line = reader.readLine();
        if (line == null)
            break;
```

 Copyright © Huawei Technologies Co., Ltd.

```
        Log.i("GetObject", "\n" + line);
    }
    reader.close();
}
```

NOTE

- When you call **ObsClient.getObject**, an instance of **ObsObject** will be returned. This instance contains the content and properties of the object.
- When you call **ObsObject.getObjectContent** to obtain an object input stream, you can read the input stream to obtain its contents. Close the input stream after use.
- For more information, see **Object Download Overview**.

3.10 Listing Objects

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

After objects are uploaded, you may want to view the objects contained in a bucket. Sample code is as follows:

```
ObjectListing objectListing = obsClient.listObjects("bucketname");
for(ObsObject obsObject : objectListing.getObjects()){
    Log.i("ListObjects", " - " + obsObject.getObjectKey() + "  " +  "(size = " +
obsObject.getMetadata().getContentLength() + ")");
}
```

NOTE

- When you call **ObsClient.listObjects**, an instance of **ObjectListing** will be returned. This instance contains the response of the **listObject** request. You can use **ObjetListing.getObjects** to obtain description of all of the listed objects.
- In the previous sample code, 1000 objects will be listed, by default.
- For more information, see **Listing Objects**.

3.11 Deleting an Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

This example deletes object **objectname** from bucket **bucketname**.

The example code is as follows:

```
obsClient.deleteObject("bucketname", "objectname");
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- This example only deletes a single object. To delete objects in a batch, traverse objects and list to-be-deleted objects on your own.
- For details about deletion, see **Deleting Objects**.

3.12 General Examples of ObsClient

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

After an API call is complete using an instance of **ObsClient**, check whether an exception is thrown. If no, the return value is valid, and an instance of the **HeaderResponse** or of its sub-class is returned. If yes, obtain the error information from the instance of **ObsException**.

For example, an OBS client uploads **localfile** to **bucketname** as **objectname**.

The example code is as follows:

```
// You can reserve only one global instance of ObsClient in your project.
// ObsClient is thread-safe and can be simultaneously used by multiple threads.
ObsClient obsClient = null;
try
{
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables AccessKeyID and SecretAccessKey.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
    String ak = System.getenv("ACCESS_KEY_ID");
    String sk = System.getenv("SECRET_ACCESS_KEY_ID");
    String endPoint = "https://your-endpoint";

    // Create an instance of ObsClient.
    obsClient = new ObsClient(ak, sk, endPoint);
    // Invoke the interface to perform operations, for example, upload an object. In the command, localfile indicates the path of the local file to be uploaded. You need to specify the file name.
    HeaderResponse response = obsClient.putObject("bucketname", "objectname", new File("localfile"));
    Log.i("PutObject", response);
}
catch (ObsException e)
{
    Log.e("PutObject", "Response Code: " + e.getResponseCode());
    Log.e("PutObject", "Error Message: " + e.getErrorMessage());
    Log.e("PutObject", "Error Code:       " + e.getErrorCode());
    Log.e("PutObject", "Request ID:      " + e.getErrorRequestId());
    Log.e("PutObject", "Host ID:           " + e.getErrorHostId());
}finally{
    // Close the instance of ObsClient. If this instance is a global one, you do not need to close it every time you complete calling a method.
    // After you call the ObsClient.close method to close an instance of ObsClient, the instance cannot be used any more.
    if(obsClient != null){
        try
        {
            obsClient.close();
```

 Copyright © Huawei Technologies Co., Ltd.

```
        }
        catch (IOException e)
        {
        }
    }
}
```

4 Initialization

4.1 Configuring the AK/SK

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

To use OBS, you need a valid pair of AK and SK for signature authentication.

For details, see **Setting Up an OBS Environment**.

After obtaining the AK/SK pair, you can start initialization by taking these steps:

- **Creating an Instance of ObsClient**
- **Configuring an Instance of ObsClient**
- **Configuring SDK Logging**

4.2 Creating an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

ObsClient functions as the Android client for accessing OBS. It offers users a series of APIs for interaction with OBS and is used for managing and performing operations on resources, such as buckets and objects, stored in OBS. To use OBS Android SDK to send a request to OBS, you need to initialize an instance of

 Copyright © Huawei Technologies Co., Ltd.

ObsClient and modify the default configurations in ObsConfiguration based on actual needs.

- If you use the endpoint to create an instance of ObsClient, all parameters are in their default values and cannot be modified. Sample code is as follows:
  - Sample code for creating an instance of ObsClient using permanent access keys (AK/SK):

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Use the instance to access OBS.

// Close ObsClient.
obsClient.close();
```

  - Sample code for creating an instance of ObsClient using temporary access keys (AK/SK and security token):

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String securityToken = "*** Provide your Security Token ***";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, securityToken, endPoint);

// Use the instance to access OBS.

// Close ObsClient.
obsClient.close();
```

NOTICE

OBS is a global service. When obtaining temporary access keys, set the token scope to **domain** to apply the token to global services. Global services are not differentiated by any project or region.

- If you use ObsConfiguration to create an instance of ObsClient, you can set configuration parameters as needed during the creation. After the instance is created, the parameters cannot be modified. For parameter details, see **Configuring an Instance of ObsClient**. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
```

 Copyright © Huawei Technologies Co., Ltd.

```
String endPoint = "https://your-endpoint";
// Create an instance of ObsConfiguration.
ObsConfiguration config = new ObsConfiguration();
config.setEndPoint(endPoint);
config.setSocketTimeout(30000);
config.setMaxErrorRetry(1);

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, config);

// Use the instance to access OBS.

// Close ObsClient.
obsClient.close();
```

NOTE

- The project can contain one or more instances of ObsClient.
- ObsClient is thread-safe and can be simultaneously used by multiple threads.

NOTICE

After you call **ObsClient.close** to close an instance of ObsClient, the instance cannot be used anymore.

4.3 Configuring an Instance of ObsClient

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

When you call the **ObsConfiguration** configuration class to create an instance of **ObsClient**, you can configure the agent, timeout duration, maximum allowed number of connections, and some other parameters listed in the following table.

Parameter	Description	Method	Recommended Value
connectionTimeout	Timeout period for establishing an HTTP/HTTPS connection, in ms. The default value is **60000**.	ObsConfiguration.setConnectionTimeout	[10000, 60000]

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method	Recommended Value
socketTimeout	Timeout duration for transmitting data at the Socket layer, in ms. The default value is **60000**.	ObsConfiguration.setSocketTimeout	[10000, 60000]
idleConnectionTime	Allowed connection idle time, in ms. If a connection exceeds the specified value, the connection will be closed. The default value is **30000**.	ObsConfiguration.setIdleConnectionTime	Default value
maxIdleConnections	Maximum number of allowed idle connections in the connection pool. The default value is **1000**.	ObsConfiguration.setMaxIdleConnections	N/A
maxConnections	Maximum number of concurrent HTTP requests. The default value is 1000.	ObsConfiguration.setMaxConnections	Default value
maxErrorRetry	Maximum number of retry attempts (caused by abnormal requests, **500**, **503**, and other errors). The default value is **3**. **NOTE** This parameter is invalid in object upload and download APIs if an interruption occurs after an upload or download task enters the data flow processing phase. In this case, no retry is performed.	ObsConfiguration.setMaxErrorRetry	[0, 5]

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method	Recommended Value
endPoint	Endpoint for accessing OBS, which contains the protocol type, domain name (or IP address), and port number. For example, https://your-endpoint:443. For security purposes, you are advised to use HTTPS.	ObsConfiguration.setEndPoint	N/A
httpProxy	HTTP proxy configuration. This parameter is left blank by default.	ObsConfiguration.setHttpProxy	N/A
validateCertificate	Whether to verify the server certificate. The default value is **false**.	ObsConfiguration.setValidateCertificate	N/A
verifyResponseContentType	Whether to verify **ContentType** of the response header. The default value is **true**.	ObsConfiguration.setVerifyResponseContentType	Default value
uploadStreamRetryBufferSize	Size of the cache used for uploading a stream object, in bytes. The default size is 512 KB.	ObsConfiguration.setUploadStreamRetryBuffer-Size	N/A
readBufferSize	Cache size for downloading the object from socket streams, in bytes. Value **-1** indicates that cache is not configured. The default value is **-1**.	ObsConfiguration.setReadBufferSize	N/A

Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method	Recommended Value
writeBufferSize	Cache size for uploading the object to socket streams, in bytes. Value **-1** indicates that cache is not configured. The default value is **-1**.	ObsConfiguration.setWriteBufferSize	N/A
socketWriteBufferSize	Buffer size for sending a socket, in bytes. This parameter corresponds to **java.net.SocketOptions.SO_SNDBUF**. The default value is **-1**, which indicates no limitation.	ObsConfiguration.setSocketWriteBufferSize	Default value
socketReadBufferSize	Buffer size for receiving a socket, in bytes. This parameter corresponds to **java.net.SocketOptions.SO_RCVBUF**. The default value is **-1**, which indicates no limitation.	ObsConfiguration.setSocketReadBufferSize	Default value
keyManagerFactory	Factory used for generating **javax.net.ssl.KeyManager**. This parameter is left blank by default.	ObsConfiguration.setKeyManagerFactory	N/A
trustManagerFactory	Factory used for generating **javax.net.ssl.TrustManager**. This parameter is left blank by default.	ObsConfiguration.setTrustManagerFactory	N/A
isStrictHostnameVerification	Whether to strictly verify the server-side host name. The default value is **false**.	ObsConfiguration.setIsStrictHostnameVerification	N/A

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method	Recommended Value
keepAlive	Whether to use persistent connections to access OBS. The default value is **true**.	ObsConfiguration.setKeepAlive	N/A
cname	Whether to use self-defined domain name to access OBS. The default value is **false**.	ObsConfiguration.setCname	N/A
sslProvider	Provider of **SSLContext**. The **SSLContext** provided by JDK is used by default.	ObsConfiguration.setSslProvider	N/A
httpProtocolType	HTTP protocol type used for accessing OBS servers. The default protocol is HTTP 1.1.	ObsConfiguration.setHttpProtocolType	N/A
httpDispatcher	Customized dispatcher	ObsConfiguration.setHttpDispatcher	N/A

NOTE

- Parameters whose recommended value is **N/A** need to be set according to the actual conditions.
- To improve the upload and download performance of large files in the case that the network bandwidth meets the requirements, you can tune the **socketWriteBufferSize**, **sockeReadBufferSize**, **readBufferSize**, and **writeBufferSize** parameters.
- If the network is unstable, you are advised to set larger values for **connectionTimeout** and **socketTimeout**.
- If the value of **endPoint** does not contain any protocol, HTTPS is used by default.
- For the sake of high DNS resolution performance and OBS reliability, you can set **endPoint** only to the domain name of OBS, instead of the IP address.

 Copyright © Huawei Technologies Co., Ltd.

4.4 Configuring SDK Logging

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS Android SDK provides the logging function based on the **java.util.logging** library. You can use **LogConfigurator.enableLog** to enable or use **LogConfigurator.disableLog** to disable the logging function. Sample code is as follows:

```
// Set the log level. The default value is LogConfigurator.WARN.
LogConfigurator.setLogLevel(LogConfigurator.INFO);

// Set the number of reserved log files. The default value is 10.
LogConfigurator.setLogFileRolloverCount(5);

// Set the size of each log file, in bytes. The size is not limited by default.
LogConfigurator.setLogFileSize(1024 * 1024 * 10);

// Set the directory for storing log files. The log files are saved in the logs directory of the SD card by default. In this sample, /storage/sdcard is used. You can change it as required.
LogConfigurator.setLogFileDir("/storage/sdcard");

// Enable logging.
LogConfigurator.enableLog();

// Disable logging.
LogConfigurator.disableLog();
```

NOTE

- The logging function is disabled by default. You need to enable it manually.
- For details about SDK logs, see **Log Analysis**.
- If no save directory of log files is configured, log files will be saved in the **logs** directory of the SD card, by default.

Copyright © Huawei Technologies Co., Ltd.

5 Bucket Management

5.1 Creating a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.createBucket** to create a bucket.

Creating a Bucket with Parameters Specified

When creating a bucket, you can specify the ACL, storage class, and location for the bucket. OBS provides three storage classes for buckets. For details, see **Storage Class**. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObsBucket obsBucket = new ObsBucket();
obsBucket.setBucketName("bucketname");
// Set the ACL for the bucket to public read (the default state is private).
obsBucket.setAcl(AccessControlList.REST_CANNED_PUBLIC_READ);
// Set the storage class to Archive.
obsBucket.setBucketStorageClass(StorageClassEnum.COLD);
// Set the bucket location.
obsBucket.setLocation("bucketlocation");
// Create a bucket.
try{
    // The bucket is successfully created.
    HeaderResponse response =obsClient.createBucket(obsBucket);
```

 Copyright © Huawei Technologies Co., Ltd.

```
    Log.i("CreateBucket", response.getRequestId());
}
catch (ObsException e)
{
    // Failed to create a bucket.
    Log.e("CreateBucket", "Response Code: " + e.getResponseCode());
    Log.e("CreateBucket", "Error Message: " + e.getErrorMessage());
    Log.e("CreateBucket", "Error Code:       " + e.getErrorCode());
    Log.e("CreateBucket", "Request ID:      " + e.getErrorRequestId());
    Log.e("CreateBucket", "Host ID:           " + e.getErrorHostId());
}
```

Creating a Bucket Directly

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Create a bucket.
try{
    // The bucket is successfully created.
    HeaderResponse response = obsClient.createBucket("bucketname");
    Log.i("CreateBucket", response.getRequestId());
}
catch (ObsException e)
{
    // Failed to create a bucket.
    Log.e("CreateBucket", "Response Code: " + e.getResponseCode());
    Log.e("CreateBucket", "Error Message: " + e.getErrorMessage());
    Log.e("CreateBucket", "Error Code:       " + e.getErrorCode());
    Log.e("CreateBucket", "Request ID:      " + e.getErrorRequestId());
    Log.e("CreateBucket", "Host ID:           " + e.getErrorHostId());
}
```

NOTE

- Bucket names are globally unique. Ensure that the bucket you create is named differently from any other bucket.
- A bucket name must comply with the following rules:
  - Contains 3 to 63 characters, chosen from lowercase letters, digits, hyphens (-), and periods (.), and starts with a digit or letter.
  - Cannot be an IP address or similar.
  - Cannot start or end with a hyphen (-) or period (.)
  - Cannot contain two consecutive periods (.), for example, **my..bucket**.
  - Cannot contain periods (.) and hyphens (-) adjacent to each other, for example, **my-.bucket** or **my.-bucket**.
- If you create buckets of the same name in a region, no error will be reported and the bucket properties comply with those set in the first creation request.
- The bucket created in the example is of the default **ACL** (private), in the OBS Standard storage class, and in the default region.

 Copyright © Huawei Technologies Co., Ltd.

NOTICE

- During bucket creation, if the endpoint you use corresponds to the default region CN North-Beijing1 (cn-north-1), specifying a region is not a must. If the endpoint you use corresponds to any other region, except the default one, you must set the region to the one that the used endpoint corresponds to. For more information about the valid regions, see **Regions and Endpoints**.
- You can specify a region for a bucket during bucket creation. For details, see **Creating a Bucket with Parameters Specified**.

5.2 Listing Buckets

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.listBuckets** to list buckets. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// List buckets.
ListBucketsRequest request = new ListBucketsRequest();
request.setQueryLocation(true);
List<ObsBucket> buckets = obsClient.listBuckets(request);
for(ObsBucket bucket : buckets){
    Log.i("ListBuckets", "BucketName" + bucket.getBucketName());
    Log.i("ListBuckets", "CreationDate" + bucket.getCreationDate());
    Log.i("ListBuckets", "Location:" + bucket.getLocation());
}
```

NOTE

- Obtained bucket names are listed in the lexicographical order.
- Set **ListBucketsRequest.setQueryLocation** to query the bucket location when listing buckets.

Copyright © Huawei Technologies Co., Ltd.

5.3 Deleting a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.deleteBucket** to delete a bucket. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Delete a bucket.
obsClient.deleteBucket("bucketname");
```

NOTE

- Only empty buckets (without objects and part fragments) can be deleted.
- Bucket deletion is a non-idempotence operation and an error will be reported if the to-be-deleted bucket does not exist.

5.4 Identifying Whether a Bucket Exists

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.headBucket** to identify whether a bucket exists.

This example checks whether bucket **bucketname** exists.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
```


Copyright © Huawei Technologies Co., Ltd.

```
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

boolean exists = obsClient.headBucket("bucketname");
```

NOTE

- If an exception is thrown and the returned HTTP status code is **404**, the bucket does not exist.

5.5 Obtaining Bucket Metadata

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketMetadata** to obtain the metadata of a bucket.

This example returns the metadata of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketMetadataInfoRequest request = new BucketMetadataInfoRequest("bucketname");
request.setOrigin("http://www.a.com");
//Obtain bucket metadata.
BucketMetadataInfoResult result = obsClient.getBucketMetadata(request);
Log.i("GetBucketMetadata", "\t:" + result.getDefaultStorageClass());
Log.i("GetBucketMetadata", "\t:" + result.getAllowOrigin());
Log.i("GetBucketMetadata", "\t:" + result.getMaxAge());
Log.i("GetBucketMetadata", "\t:" + result.getAllowHeaders());
Log.i("GetBucketMetadata", "\t:" + result.getAllowMethods());
Log.i("GetBucketMetadata", "\t:" + result.getExposeHeaders());
```

NOTE

- For details about values of methods, such as **BucketMetadataInfoResult.getAllowMethods**, see the **CORS** configurations of the bucket.

5.6 Managing Bucket ACLs

Access control lists (ACLs) allow resource owners to grant other accounts the permissions to access resources. By default, only the resource owner has full

 Copyright © Huawei Technologies Co., Ltd.

control over resources when a bucket or object is created. That is, the bucket creator has full control over the bucket, and the object uploader has full control over the object. Other accounts do not have the permissions to access resources. If resource owners want to grant other accounts the read and write permissions on resources, they can use ACLs. ACLs grant permissions to accounts. After an account is granted permissions, both the account and its IAM users can access the resources.

For more information, see **ACLs**.

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

A bucket ACL can be configured in any of the following ways:

1. Specify a pre-defined ACL when creating a bucket.
2. Call ObsClient.setBucketAcl to specify a pre-defined ACL.
3. Call ObsClient.setBucketAcl to specify a user-defined ACL.

OBS supports five types of bucket or object ACL configuration items, as listed in the following table:

Permission	Description	Value in OBS Android SDK
READ	A grantee with this permission for a bucket can obtain the list of objects in and metadata of the bucket. A grantee with this permission for an object can obtain the object content and metadata.	Permission.PERMISSION_READ
WRITE	A grantee with this permission for a bucket can upload, overwrite, and delete any object in the bucket. This permission is not applicable to objects.	Permission.PERMISSION_WRITE
READ_ACP	A grantee with this permission can obtain the ACL of a bucket or object. A bucket or object owner has this permission permanently.	Permission.PERMISSION_READ_ACP

 Copyright © Huawei Technologies Co., Ltd.

Permission	Description	Value in OBS Android SDK
WRITE_ACP	A grantee with this permission can update the ACL of a bucket or object. A bucket or object owner has this permission permanently. A grantee with this permission can modify the access control policy and thus the grantee obtains full access permissions.	Permission.PERMISSION_WRITE_ACP
FULL_CONTROL	A grantee with this permission for a bucket has **READ**, **WRITE**, **READ_ACP**, and **WRITE_ACP** permissions for the bucket. A grantee with this permission for an object has **READ**, **READ_ACP**, and **WRITE_ACP** permissions for the object.	Permission.PERMISSION_FULL_CONTROL

There are five access control policies pre-defined in OBS, as described in the following table:

Policy	Description	Value in OBS Android SDK
private	The owner of a bucket or object has the **FULL_CONTROL** permission for the bucket or object. Other users have no permission to access the bucket or object.	AccessControlList.REST_CANNED_PRIVATE
public-read	If this permission is set for a bucket, everyone can obtain the list of objects, multipart uploads, and object versions in the bucket, as well as metadata of the bucket. If this permission is set for an object, everyone can obtain the content and metadata of the object.	AccessControlList.REST_CANNED_PUBLIC_READ

 Copyright © Huawei Technologies Co., Ltd.

Policy	Description	Value in OBS Android SDK
public-read-write	If this permission is set for a bucket, everyone can obtain the object list in the bucket, multipart uploads in the bucket, metadata of the bucket; upload objects; delete objects; initialize multipart uploads; upload parts; combine parts; copy parts; and abort multipart uploads. If this permission is set for an object, everyone can obtain the content and metadata of the object.	AccessControlList.REST_CANNED_PUBLIC_READ_WRITE
public-read-delivered	If this permission is set for a bucket, everyone can obtain the object list, multipart uploads, and bucket metadata in the bucket, and obtain the content and metadata of the objects in the bucket. This permission cannot be set for objects.	AccessControlList.REST_CANNED_PUBLIC_READ_DELIVERED
public-read-write-delivered	If this permission is set for a bucket, everyone can obtain the object list in the bucket, multipart uploads in the bucket, metadata of the bucket; upload objects; delete objects; initialize multipart uploads; upload parts; combine parts; copy parts; abort multipart uploads; and obtain content and metadata of objects in the bucket. This permission cannot be set for objects.	AccessControlList.REST_CANNED_PUBLIC_READ_WRITE_DELIVERED

Specifying a Pre-defined ACL During Bucket Creation

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
```

 Copyright © Huawei Technologies Co., Ltd.

```
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObsBucket obsBucket = new ObsBucket();
obsBucket.setBucketName("bucketname");
// Set the ACL to public read and write.
obsBucket.setAcl(AccessControlList.REST_CANNED_PUBLIC_READ_WRITE);
// Create a bucket.
obsClient.createBucket(obsBucket);
```

Setting a Pre-defined ACL for a Bucket

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set the bucket ACL to private read and write.
obsClient.setBucketAcl("bucketname", AccessControlList.REST_CANNED_PRIVATE);
```

Setting a User-defined Bucket ACL

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AccessControlList acl = new AccessControlList();
Owner owner = new Owner();
owner.setId("ownerid");
acl.setOwner(owner);
// Grant the FULL_CONTROL permission to a specified user.
acl.grantPermission(new CanonicalGrantee("userid"), Permission.PERMISSION_FULL_CONTROL);
// Grant the READ permission to all users.
acl.grantPermission(GroupGrantee.ALL_USERS, Permission.PERMISSION_READ);
// Set the bucket ACL.
obsClient.setBucketAcl("bucketname", acl);
```

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining a Bucket ACL

You can call ObsClient.getBucketAcl to obtain a bucket ACL. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

 Copyright © Huawei Technologies Co., Ltd.

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AccessControlList acl = obsClient.getBucketAcl("bucketname");
Log.i("GetBucketAcl", acl.toString());
```

5.7 Managing Bucket Policies

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Besides bucket ACLs, bucket owners can use bucket policies to centrally control access to buckets and objects in buckets.

For more information, see **Bucket Policy**.

Setting a Bucket Policy

You can call **ObsClient.setBucketPolicy** to set a bucket policy. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
obsClient.setBucketPolicy("bucketname", "your policy");
```

NOTE

For details about the format (JSON character string) of bucket policies, see the *Object Storage Service API Reference*.

Obtaining a Bucket Policy

You can call **ObsClient.getBucketPolicy** to obtain a bucket policy. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/
```

 Copyright © Huawei Technologies Co., Ltd.

```
intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

String policy = obsClient.getBucketPolicy("bucketname");
Log.i("GetBucketPolicy","\t" + policy);
```

Deleting a Bucket Policy

You can call **ObsClient.deleteBucketPolicy** to delete a bucket policy. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

obsClient.deleteBucketPolicy("bucketname");
```

5.8 Obtaining a Bucket Location

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketLocation** to obtain the location of a bucket.

This example returns the region of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

String location = obsClient.getBucketLocation("bucketname");
Log.i("GetBucketLocation", "\t:" + location);
```

NOTE

- When creating a bucket, you can specify its location. For details, see **Creating a Bucket**.

 Copyright © Huawei Technologies Co., Ltd.

5.9 Obtaining Storage Information About a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

The storage information about a bucket includes the used capacity of and the number of objects in the bucket.

You can call **ObsClient.getBucketStorageInfo** to obtain the bucket storage information.

This example returns the storage information of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketStorageInfo storageInfo = obsClient.getBucketStorageInfo("bucketname");
Log.i("GetBucketStorageInfo", "\t" + storageInfo.getObjectNumber());
Log.i("GetBucketStorageInfo", "\t" + storageInfo.getSize());
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

5.10 Setting or Obtaining a Bucket Quota

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Setting a Bucket Quota

You can call **ObsClient.setBucketQuota** to set the bucket quota. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

 Copyright © Huawei Technologies Co., Ltd.

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set the bucket quota to 100 MB.
BucketQuota quota = new BucketQuota(1024 * 1024 * 100);
obsClient.setBucketQuota("bucketname", quota);
```

NOTE

A bucket quota must be a non-negative integer expressed in bytes. The maximum value is 2^{63} - 1.

Obtaining a Bucket Quota

You can call **ObsClient.getBucketQuota** to obtain a bucket quota. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketQuota quota = obsClient.getBucketQuota("bucketname");
Log.i("GetBucketQuota", "\t" + quota.getBucketQuota());
```

5.11 Storage Class

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS allows you to set storage classes for buckets. The storage class of an object defaults to be that of its residing bucket. Different storage classes meet different needs for storage performance and costs. There are three types of storage class for buckets, as described in the following table:

 Copyright © Huawei Technologies Co., Ltd.

Storage Class	Description	Value in OBS Android SDK
OBS Standard	Features low access latency and high throughput and is applicable to storing frequently-accessed (multiple times per month) hotspot or small objects (< 1 MB) requiring quick response.	StorageClassEnum.STANDARD
OBS Infrequent Access	Is applicable to storing semi-frequently accessed (less than 12 times a year) data requiring quick response.	StorageClassEnum.WARM
OBS Archive	Is applicable to archiving rarely-accessed (once a year) data.	StorageClassEnum.COLD

For more information, see **Bucket Storage Classes**.

Setting the Storage Class for a Bucket

You can call **ObsClient.setBucketStoragePolicy** to set the storage class for a bucket. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set the storage class to Infrequent Access.
BucketStoragePolicyConfiguration storgePolicy = new BucketStoragePolicyConfiguration();
storgePolicy.setBucketStorageClass(StorageClassEnum.WARM);
obsClient.setBucketStoragePolicy("bucketname", storgePolicy);
```

Obtaining the Storage Class of a Bucket

You can call **ObsClient.getBucketStoragePolicy** to obtain the storage class of a bucket. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
```

 Copyright © Huawei Technologies Co., Ltd.

```
BucketStoragePolicyConfiguration storagePolicy = obsClient.getBucketStoragePolicy("bucketname");
Log.i("GetBucketStoragePolicy", "\t" + storagePolicy.getBucketStorageClass());
```

 Copyright © Huawei Technologies Co., Ltd.

6 Object Upload

6.1 Object Upload Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

In OBS, objects are basic data units that users can perform operations on. OBS Android SDK provides abundant APIs for object upload in the following methods:

- **Performing a Streaming Upload**
- **Performing a File-Based Upload**
- **Performing a Multipart Upload**
- **Performing an Appendable Upload**
- **Performing a Resumable Upload**
- **Performing a Browser-Based Upload**

The SDK supports the upload of objects whose size ranges from 0 KB to 5 GB. For streaming upload, appendable upload, and file-based upload, data to be uploaded cannot be larger than 5 GB. If the file is larger than 5 GB, multipart upload (whose part size is smaller than 5 GB) is suitable. Browser-based upload allows files to be uploaded through a browser.

If you grant anonymous users the read permission for an object during the upload, anonymous users can access the object through a URL after the upload is complete. The object URL is in the format of **https://*bucket name.domain name*/*directory levels*/*object name***. If the object resides in the root directory of a bucket, its URL does not contain directory levels.

 Copyright © Huawei Technologies Co., Ltd.

NOTE

In the following codes, "bucketname" indicates the name of the bucket to which the object is to be uploaded. "objectname" is the name of the target object that is expected to be generated in the bucket after the upload. The directory levels can be specified, for example, **src/src1/src2/test.txt**. If no directory level is specified, the object is uploaded to the root directory of the bucket.

6.2 Performing a Streaming Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Streaming upload uses **java.io.InputStream** as the data source of an object. You can call **ObsClient.putObject** to upload the data streams to OBS. Sample code is as follows:

Uploading a Character String (Byte Array)

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

String content = "Hello OBS";
obsClient.putObject("bucketname", "objectname", new ByteArrayInputStream(content.getBytes()));
```

Uploading a Network Stream

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

InputStream inputStream = new URL("http://www.a.com").openStream();
obsClient.putObject("bucketname", "objectname", inputStream);
```

Uploading a File Stream

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
```

 Copyright © Huawei Technologies Co., Ltd.

```
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

FileInputStream fis = new FileInputStream(new File("localfile")); // localfile indicates the path of the local file to be uploaded. You need to specify the file name.
obsClient.putObject("bucketname", "objectname", fis);
// Path of the local file to be uploaded, in which the file name must be specified.
FileInputStream fis2 = new FileInputStream(new File("localfile2"));
PutObjectRequest request = new PutObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("objectname2");
request.setInput(fis2);
obsClient.putObject(request);
```

NOTE

- To upload a local file, you are advised to use **file-based upload**.
- To upload a large file, you are advised to use **multipart upload**.
- The file to be uploaded cannot exceed 5 GB.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **PutObjectRequest.setIsEncodeHeaders(false)** to disable auto encoding.

6.3 Performing a File-Based Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

File-based upload uses local files as the data source of objects. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
try {
    // Upload a file.
    // localfile indicates the path of the local file to be uploaded, which must include the file name.
    PutObjectRequest request = new PutObjectRequest();
    request.setBucketName("examplebucket");
    request.setObjectKey("objectkey");
    request.setFile(new File("localfile"));
```

 Copyright © Huawei Technologies Co., Ltd.

```
    obsClient.putObject(request);
    System.out.println("putObject successfully");
} catch (ObsException e) {
    System.out.println("putObject failed");
    // Request failed. Print the HTTP status code.
    System.out.println("HTTP Code:" + e.getResponseCode());
    // Request failed. Print the server-side error code.
    System.out.println("Error Code:" + e.getErrorCode());
    // Request failed. Print the error details.
    System.out.println("Error Message:" + e.getErrorMessage());
    // Request failed. Print the request ID.
    System.out.println("Request ID:" + e.getErrorRequestId());
    System.out.println("Host ID:" + e.getErrorHostId());
    e.printStackTrace();
} catch (Exception e) {
    System.out.println("putObject failed");
    // Print other error details.
    e.printStackTrace();
}
```

NOTE

- The file to be uploaded cannot exceed 5 GB.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **PutObjectRequest.setIsEncodeHeaders(false)** to disable auto encoding. To use auto encoding, you need to install the latest version of the SDK.

6.4 Obtaining Upload Progresses

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **PutObjectRequest.setProgressListener** to configure the data transmission interface to obtain upload progresses. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

PutObjectRequest request = new PutObjectRequest("bucketname", "objectname");
request.setFile(new File("localfile")); // localfile indicates the path of the local file to be uploaded. You need to specify the file name.
request.setProgressListener(new ProgressListener() {

    @Override
    public void progressChanged(ProgressStatus status) {
```

 Copyright © Huawei Technologies Co., Ltd.

```
            // Obtain the average upload rate.
            Log.i("PutObject", "AverageSpeed:" + status.getAverageSpeed());
            // Obtain the upload progress in percentage.
            Log.i("PutObject", "TransferPercentage:" + status.getTransferPercentage());
        }
});
// Refresh the upload progress each time 1 MB data is uploaded.
request.setProgressInterval(1024 * 1024L);
obsClient.putObject(request);
```

NOTE

- You can query the upload progress when uploading an object in streaming, file-based, multipart, appendable, or resumable mode.
- If the value of **ProgressStatus.getTransferPercentage()** is **-1**, the content is uploaded in streaming mode. In this case, you must set the object length (**Content-Length**) in the object attribute.

6.5 Creating a Folder

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

There is no folder concept in OBS. All elements in buckets are objects. To create a folder in OBS is essentially to create an object whose size is 0 and whose name ends with a slash (/). Such objects have no difference from other objects and can be downloaded and deleted, except that they are displayed as folders in OBS Console.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

final String keySuffixWithSlash = "parent_directory/";
obsClient.putObject("bucketname", keySuffixWithSlash, new ByteArrayInputStream(new byte[0]));

// In the folder, create an object.
obsClient.putObject("bucketname", keySuffixWithSlash + "objectname", new ByteArrayInputStream("Hello OBS".getBytes()));
```

NOTE

- To create a folder in OBS is to create an object whose size is 0 and whose name ends with a slash (/), in essential.
- To create a multi-level folder, you only need to create the folder with the last level. For example, if you want to create a folder named **src1/src2/src3/**, create it directly, no matter whether the **src1/** and **src1/src2/** folders exist.

 Copyright © Huawei Technologies Co., Ltd.

6.6 Setting Object Properties

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can set properties for an object when uploading it. Object properties include the object length, MIME type, MD5 value (for verification), and customized metadata. You can set properties for an object that is being uploaded in streaming, file-based, or multipart mode or when **copying the object**.

The following table describes object properties.

Property Name	Description	Default Value
Content-Length	Indicates the object length. If the object length exceeds the flow or file length, the object will be truncated.	Actual length of the stream or file
Content-Type	Indicates the MIME type of the object, which defines the type and network code of the object as well as in which mode and coding will the browser read the object.	application/octet-stream
Content-MD5	Indicates the base64-encoded digest of the object data. It is provided to the OBS server to verify data integrity.	N/A
Storage class	Indicates the storage class of the object. Different storage classes meet different needs for storage performance and costs. The value defaults to be the same as the object's residing bucket and can be changed.	N/A

Copyright © Huawei Technologies Co., Ltd.

Property Name	Description	Default Value
Customized metadata	Indicates the user-defined description of the object. It is used to facilitate the customized management on the object.	N/A

Setting the Length for an Object

You can call **ObjectMetadata.setContentLength** to set the length for an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObjectMetadata metadata = new ObjectMetadata();
metadata.setContentLength(1024 * 1024L);//1 MB
obsClient.putObject("bucketname", "objectname", new File("localfile"), metadata);
```

Setting the MIME Type for an Object

You can call **ObjectMetadata.setContentType** to set the MIME type for an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Upload an image.
ObjectMetadata metadata = new ObjectMetadata();
metadata.setContentType("image/jpeg");
obsClient.putObject("bucketname", "objectname", new File("localimage.jpg"), metadata);
```

NOTE

If this property is not specified, the SDK will automatically identify the MIME type according to the name suffix of the uploaded object. For example, if the name suffix of an object is **.xml** (**.html**), the object will be identified as an application/xml (text/html) file.

 Copyright © Huawei Technologies Co., Ltd.

Setting the MD5 Value for an Object

You can call **ObjectMetadata.setContentMd5** to set the MD5 value for an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Upload an image.
ObjectMetadata metadata = new ObjectMetadata();
metadata.setContentMd5("your md5 which should be encoded by base64");
obsClient.putObject("bucketname", "objectname", new File("localimage.jpg"), metadata);
```

NOTE

- The MD5 value of an object must be a base64-encoded digest.
- The OBS server will compare this MD5 value with the MD5 value obtained by object data calculation. If the two values are not the same, the upload fails with HTTP status code **400** returned.
- If the MD5 value is not specified, the OBS server will skip MD5 value verification.
- You can call **ObsClient.base64Md5** to calculate the **Content-MD5** header directly.

Setting the Storage Class for an Object

You can call **ObjectMetadata.setStorageClass** to set the storage class for an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObjectMetadata metadata = new ObjectMetadata();
// Set the storage class to Infrequent Access.
metadata.setObjectStorageClass(StorageClassEnum.WARM);
obsClient.putObject("bucketname", "objectname", new File("localfile"), metadata);
```

NOTE

- If you do not set the storage class for an object, the storage class of the object will be the same as that of its residing bucket.
- OBS provides objects with three storage classes which are consistent with **those** provided for buckets.
- Before downloading an Archive object, you must restore it first.

 Copyright © Huawei Technologies Co., Ltd.

Customizing Metadata for an Object

You can call **ObjectMetadata.addUserMetadata** to customize metadata for an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObjectMetadata metadata = new ObjectMetadata();
metadata.addUserMetadata("property1", "property-value1");
metadata.getMetadata().put("property2", "property-value2");
obsClient.putObject("bucketname", "objectname", new File("localfile"), metadata);
```

NOTE

- In the preceding code, two pieces of metadata named **property1** and **property2** are customized and their respective values are set to **property-value1** and **property-value2**.
- An object can have multiple pieces of metadata whose size cannot exceed 8 KB.
- The custom object metadata can be obtained by using **ObsClient.getObjectMetadata**. For details, see **Obtaining Object Attributes**.
- When you call **ObsClient.getObject** to download an object, its customized metadata will also be downloaded.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **PutObjectRequest.setIsEncodeHeaders(false)** to disable auto encoding.

6.7 Performing a Multipart Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

To upload a large file, multipart upload is recommended. Multipart upload is applicable to many scenarios, including:

- Files to be uploaded are larger than 100 MB.
- The network condition is poor. Connection to the OBS server is constantly down.
- Sizes of files to be uploaded are uncertain.

Multipart upload consists of three phases:

 Copyright © Huawei Technologies Co., Ltd.

Step 1 Initialize a multipart upload (**ObsClient.initiateMultipartUpload**).

Step 2 Upload parts one by one or concurrently (**ObsClient.uploadPart**).

Step 3 Combine parts (**ObsClient.completeMultipartUpload**) or abort the multipart upload (**ObsClient.abortMultipartUpload**).

----End

Initiating a Multipart Upload

Before upload, you need to notify OBS of initializing a multipart upload. This operation will return an upload ID (globally unique identifier) created by the OBS server to identify the multipart upload. You can use this upload ID to initiate related operations, such as aborting a multipart upload, listing multipart uploads, and listing uploaded parts.

You can call **ObsClient.initiateMultipartUpload** to initialize a multipart upload.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

InitiateMultipartUploadRequest request = new InitiateMultipartUploadRequest("bucketname", "objectname");
ObjectMetadata metadata = new ObjectMetadata();
metadata.addUserMetadata("property", "property-value");
metadata.setContentType("text/plain");
request.setMetadata(metadata);
InitiateMultipartUploadResult result = obsClient.initiateMultipartUpload(request);

String uploadId = result.getUploadId();
Log.i("InitiateMultipartUpload", "\t" + uploadId);
```

NOTE

- Call **InitiateMultipartUploadRequest** to specify the name and owning bucket of the uploaded object.
- In **InitiateMultipartUploadRequest**, you can specify the MIME type, storage class, and customized metadata for the object.
- The upload ID of the multipart upload returned by **InitiateMultipartUploadResult.getUploadId** will be used in follow-up operations.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **InitiateMultipartUploadRequest.setIsEncodeHeaders(false)** to disable auto encoding.

Uploading a Part

After initializing a multipart upload, you can specify the object name and upload ID to upload a part. Each upload part has a part number (ranging from 1 to

 Copyright © Huawei Technologies Co., Ltd.

10000). For parts with the same upload ID, their part numbers are unique and identify their comparative locations in the object. If you use the same part number to upload two parts, the latter one being uploaded will overwrite the former. Except for the part last uploaded whose size ranges from 0 to 5 GB, sizes of the other parts range from 100 KB to 5 GB. Parts are uploaded in random order and can be uploaded through different processes or machines. OBS will combine them into the object based on their part numbers.

You can call **ObsClient.uploadPart** to upload a part.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

List<PartEtag> partEtags = new ArrayList<PartEtag>();
// Upload the first part.
UploadPartRequest request = new UploadPartRequest("bucketname", "objectname");
// Set the upload ID.
request.setUploadId(uploadId);
// Set the part number, which ranges from 1 to 10000.
request.setPartNumber(1);
// Set the large file to be uploaded. localfile is the path of the local file to be uploaded. You need to specify the file name.
request.setFile(new File("localfile"));

// Set the part size.
request.setPartSize(5 * 1024 * 1024L);
UploadPartResult result = obsClient.uploadPart(request);
partEtags.add(new PartEtag(result.getEtag(), result.getPartNumber()));

// Upload the second part.
request = new UploadPartRequest("bucketname", "objectname");
// Set the upload ID.
request.setUploadId(uploadId);
// Set the part number.
request.setPartNumber(2);
// Set the large file to be uploaded.
request.setFile(new File("localfile"));
// Set the offset for the second part.
request.setOffset(5 * 1024 * 1024L);
// Set the part size.
request.setPartSize(5 * 1024 * 1024L);
result = obsClient.uploadPart(request);
partEtags.add(new PartEtag(result.getEtag(), result.getPartNumber()));
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- Except the part last uploaded, other parts must be larger than 100 KB. Part sizes will not be verified during upload because which one is last uploaded is not identified until parts are combined.
- OBS will return ETags (MD5 values) of the received parts to users.
- To ensure data integrity, set **UploadPartRequest.setAttachMd5** to **true** to make the SDK automatically calculate the MD5 value (valid only when the data source is a local file) of each part and add the MD5 value to the **Content-MD5** request header. The OBS server will compare the MD5 value contained by each part and that calculated by the SDK to verify the data integrity.
- You can call **UploadPartRequest.setContentMd5** to set the MD5 value of the uploaded data directly. If this value is set, the **UploadPartRequest.setAttachMd5** parameter becomes ineffective.
- Part numbers range from 1 to 10000. If a part number exceeds this range, OBS will return **a 400 Bad Request** error.

Combining Parts

After all parts are uploaded, call the API for combining parts to generate the object. Before this operation, valid part numbers and ETags of all parts must be sent to OBS. After receiving this information, OBS verifies the validity of each part one by one. After all parts pass the verification, OBS combines these parts to form the final object.

You can call **ObsClient.completeMultipartUpload** to combine parts.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

List<PartEtag> partEtags = new ArrayList<PartEtag>();

// First part
PartEtag part1 = new PartEtag();
part1.setPartNumber(1);
part1.seteTag("etag1");
partEtags.add(part1);

// Second part
PartEtag part2 = new PartEtag();
part2.setPartNumber(2);
part2.seteTag("etag2");
partEtags.add(part2);

CompleteMultipartUploadRequest request = new CompleteMultipartUploadRequest("bucketname", "objectname", uploadId, partEtags);

obsClient.completeMultipartUpload(request);
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- In the preceding code, **partEtags** indicates the list of part numbers and ETags of uploaded parts. These parts are listed in ascending order by part number.
- Part numbers can be inconsecutive.

Concurrently Uploading Parts

Multipart upload is mainly used for large file upload or when the network condition is poor. The following sample code shows how to concurrently upload parts involved in a multipart upload:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
final String bucketName = "bucketname";
final String objectKey = "objectname";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Initialize the thread pool.
ExecutorService executorService = Executors.newFixedThreadPool(20);
final File largeFile = new File("localfile");

// Initiate a multipart upload.
InitiateMultipartUploadRequest request = new InitiateMultipartUploadRequest(bucketName, objectKey);
InitiateMultipartUploadResult result = obsClient.initiateMultipartUpload(request);

final String uploadId = result.getUploadId();
Log.i("UploadPart", "\t"+ uploadId + "\n");

// Set the part size to 100 MB.
long partSize = 100 * 1024 * 1024L;
long fileSize = largeFile.length();

// Calculate the number of parts to be uploaded.
long partCount = fileSize % partSize == 0 ? fileSize / partSize : fileSize / partSize + 1;

final List<PartEtag> partEtags = Collections.synchronizedList(new ArrayList<PartEtag>());

// Concurrently upload parts.
for (int i = 0; i < partCount; i++)
{
    // Start position of a part in the file
    final long offset = i * partSize;
    // Part size
    final long currPartSize = (i + 1 == partCount) ? fileSize - offset : partSize;
    // Part number
    final int partNumber = i + 1;
    executorService.execute(new Runnable()
    {
        @Override
        public void run()
        {
            UploadPartRequest uploadPartRequest = new UploadPartRequest();
            uploadPartRequest.setBucketName(bucketName);
            uploadPartRequest.setObjectKey(objectKey);
            uploadPartRequest.setUploadId(uploadId);
            uploadPartRequest.setFile(largeFile);
            uploadPartRequest.setPartSize(currPartSize);
            uploadPartRequest.setOffset(offset);
```

 Copyright © Huawei Technologies Co., Ltd.

```
            uploadPartRequest.setPartNumber(partNumber);

            UploadPartResult uploadPartResult;
            try
            {
                uploadPartResult = obsClient.uploadPart(uploadPartRequest);
                Log.i("UploadPart", "Part#" + partNumber + " done\n");
                partEtags.add(new PartEtag(uploadPartResult.getEtag(), uploadPartResult.getPartNumber()));
            }
            catch (ObsException e)
            {
                Log.e("UploadPart", e.getMessage(), e);
            }
        }
    });
}

// Wait until the upload is complete.
executorService.shutdown();
while (!executorService.isTerminated())
{
    try
    {
        executorService.awaitTermination(5, TimeUnit.SECONDS);
    }
    catch (InterruptedException e)
    {
        Log.e("UploadPart", e.getMessage(), e);
    }
}

// Combine parts.
CompleteMultipartUploadRequest completeMultipartUploadRequest =
    new CompleteMultipartUploadRequest(bucketName, objectKey, uploadId, partEtags);
obsClient.completeMultipartUpload(completeMultipartUploadRequest);
```

NOTE

When uploading a large file, use **UploadPartRequest.setOffset** and **UploadPartRequest.setPartSize** to determine the start and end positions of each part.

Aborting a Multipart Upload

After a multipart upload is aborted, you cannot use its upload ID to perform any operation and the uploaded parts will be deleted by OBS.

When an object is being uploaded in multi-part mode or an object fails to be uploaded, parts are generated in the bucket. These parts occupy your storage space. You can cancel the multi-part uploading task to delete unnecessary parts, thereby saving the storage space.

You can call **ObsClient.abortMultipartUpload** to abort a multipart upload.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AbortMultipartUploadRequest request = new AbortMultipartUploadRequest("bucketname", "objectname",
```

```
uploadId);

obsClient.abortMultipartUpload(request);
```

Listing Uploaded Parts

You can call **ObsClient.listParts** to list successfully uploaded parts of a multipart upload.

The following table describes the parameters involved in this API.

Parameter	Description	Method in OBS Android SDK
bucketName	Bucket name	ListPartsRequest.setBucketName
key	Object name	ListPartsRequest.setKey
uploadId	Upload ID, which globally identifies a multipart upload. The value is in the returned result of **ObsClient.initiateMultipartUpload**.	ListPartsRequest.setUploadId
maxParts	Maximum number of parts that can be listed per page.	ListPartsRequest.setMaxParts
partNumberMarker	Part number after which listing parts begins. Only parts whose part numbers are larger than this value will be listed.	ListPartsRequest.setPartNumberMarker

- Listing parts in simple mode

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

//List the uploaded parts. uploadId is obtained from initiateMultipartUpload.
ListPartsRequest request = new ListPartsRequest("bucketname", "objectname");
request.setUploadId(uploadId);
ListPartsResult result = obsClient.listParts(request);

for(Multipart part : result.getMultipartList()){
// Part number, specified when being uploaded
   Log.i("ListParts", "\t"+part.getPartNumber());
// Part size
   Log.i("ListParts","\t"+part.getSize());
```

 Copyright © Huawei Technologies Co., Ltd.

```
// Part ETag
   Log.i("ListParts","\t"+part.getEtag());
// Time when the part was last uploaded
   Log.i("ListParts","\t"+part.getLastModified());
}
```

NOTE

- Information about a maximum of 1000 parts can be listed each time. If an upload of the specific upload ID contains more than 1000 parts and **ListPartsResult.isTruncated** is **true** in the returned result, not all parts are listed. In such cases, you can use **ListPartsResult.getNextPartNumberMarker** to obtain the start position for next listing.
- If you want to obtain all parts involved in a specific upload ID, you can use the paging mode for listing.

- Listing all parts

If the number of parts of a multipart upload is larger than 1000, you can use the following sample code to list all parts.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

//List the uploaded parts. uploadId is obtained from initiateMultipartUpload.
ListPartsRequest request = new ListPartsRequest("bucketname", "objectname");
request.setUploadId(uploadId);
ListPartsResult result;

do{
   result = obsClient.listParts(request);
   for(Multipart part : result.getMultipartList()){
// Part number, specified when being uploaded
      Log.i("ListParts","\t"+part.getPartNumber());
// Part size
      Log.i("ListParts","\t"+part.getSize());
// Part ETag
      Log.i("ListParts","\t"+part.getEtag());
// Time when the part was last uploaded
      Log.i("ListParts","\t"+part.getLastModified());
   }
   request.setPartNumberMarker(Integer.parseInt(result.getNextPartNumberMarker()));
}while(result.isTruncated());
```

Listing Multipart Uploads

You can call **ObsClient.listMultipartUploads** to list multipart uploads. The following table describes parameters involved in **ObsClient.listMultipartUploads**.

Parameter	Description	Method in OBS Android SDK
bucketName	Bucket name	ListMultipartUploadsRequest.setBucketName

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
prefix	Prefix that the object names in the multipart uploads to be listed must contain	ListMultipartUploadsRequest.setPrefix
delimiter	Character used to group object names involved in multipart uploads. If the object name contains the **delimiter** parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, **commonPrefix**. (If a prefix is specified in the request, the prefix must be removed from the object name.)	ListMultipartUploadsRequest.setDelimiter
maxUploads	Maximum number of multipart uploads listed in the response body. The value ranges from **1** to **1000**. If the value exceeds **1000**, only 1,000 multipart uploads are returned.	ListMultipartUploadsRequest.setMaxUploads
keyMarker	Object name to start with when listing multipart uploads	ListMultipartUploadsRequest.setKeyMarker
uploadIdMarker	Upload ID after which the multipart upload listing begins. It is effective only when used with **keyMarker** so that multipart uploads after **uploadIdMarker** of **keyMarker** will be listed.	ListMultipartUploadsRequest.setUploadIdMarker

- Listing multipart uploads in simple mode

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListMultipartUploadsRequest request = new ListMultipartUploadsRequest("bucketname");

MultipartUploadListing result = obsClient.listMultipartUploads(request);
for(MultipartUpload upload : result.getMultipartTaskList()){
    Log.i("ListMultipartUploads","\t" + upload.getUploadId());
    Log.i("ListMultipartUploads","\t" + upload.getObjectKey());
```

 Copyright © Huawei Technologies Co., Ltd.

```
    Log.i("ListMultipartUploads","\t" + upload.getInitiatedDate());
}
```

NOTE

- Information about a maximum of 1000 multipart uploads can be listed each time. If a bucket contains more than 1000 multipart uploads and **MultipartUploadListing.isTruncated** is **true**, not all uploads are listed. In such cases, you can use **MultipartUploadListing.getNextKeyMarker** and **MultipartUploadListing.getNextUploadIdMarker** to obtain the start position for next listing.
- If you want to obtain all multipart uploads in a bucket, you can list them in paging mode.

- Listing all multipart uploads in paging mode

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
String uploadId = "upload id from initiateMultipartUpload";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListMultipartUploadsRequest request = new ListMultipartUploadsRequest("bucketname");
MultipartUploadListing result;

do{
    result = obsClient.listMultipartUploads(request);
    for(MultipartUpload upload : result.getMultipartTaskList()){
        Log.i("ListMultipartUploads","\t" + upload.getUploadId());
        Log.i("ListMultipartUploads","\t" + upload.getObjectKey());
        Log.i("ListMultipartUploads","\t" + upload.getInitiatedDate());
    }
    request.setKeyMarker(result.getNextKeyMarker());
    request.setUploadIdMarker(result.getNextUploadIdMarker());
}while(result.isTruncated());
```

6.8 Configuring Lifecycle Management

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

When uploading an object or initializing a multipart upload, you can directly set the expiration time for the object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
```

 Copyright © Huawei Technologies Co., Ltd.

```
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
 try {
     PutObjectRequest request = new PutObjectRequest();
     request.setBucketName("examplebucket");
     request.setObjectKey("objectname");
     request.setFile(new File("localfile"));
     // When uploading an object, configure it to expire 30 days after being uploaded.
     request.setExpires(30);
     obsClient.putObject(request);
     // InitiateMultipartUploadRequest request2 = new InitiateMultipartUploadRequest("bucketname",
"objectname");
     //// When initiating a multipart upload, configure the object to expire 60 days after being created from
part assembling.
     // request2.setExpires(60);
     //obsClient.initiateMultipartUpload(request);
     System.out.println("putObject successfully");
  } catch (ObsException e) {
     System.out.println("putObject failed");
     // Request failed. Print the HTTP status code.
     System.out.println("HTTP Code:" + e.getResponseCode());
     // Request failed. Print the server-side error code.
     System.out.println("Error Code:" + e.getErrorCode());
     // Request failed. Print the error details.
     System.out.println("Error Message:" + e.getErrorMessage());
     // Request failed. Print the request ID.
     System.out.println("Request ID:" + e.getErrorRequestId());
     System.out.println("Host ID:" + e.getErrorHostId());
     e.printStackTrace();
 } catch (Exception e) {
     System.out.println("putObject failed");
     // Print other error details.
     e.printStackTrace();
 }
```

NOTE

- This mode specifies the time duration in days after which an object will expire. The OBS server automatically clears expired objects.
- The object expiration time set in this mode takes precedence over the bucket lifecycle rule.

6.9 Performing an Appendable Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Appendable upload allows you to upload an object in appendable mode and then append data to the object. You can call **ObsClient.appendObject** to perform an appendable upload. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the
configuration file or environment variables. In this example, the AK/SK are stored in environment variables
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID
and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/
intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
```

 Copyright © Huawei Technologies Co., Ltd.

```
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Upload an object in appendable mode.
AppendObjectRequest request = new AppendObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("objectname");
request.setPosition(0L);
request.setInput(new ByteArrayInputStream("Hello OBS".getBytes()));
AppendObjectResult result = obsClient.appendObject(request);

// Append data to the object.
request.setPosition(result.getNextPosition());
request.setInput(new ByteArrayInputStream("Hello OBS Again".getBytes()));
result = obsClient.appendObject(request);

Log.i("AppendObject", "NextPosition:" + result.getNextPosition());
Log.i("AppendObject",  "Etag:" + result.getEtag());
// Use the API for obtaining object properties to get the start position for next appending.
ObjectMetadata metadata = obsClient.getObjectMetadata("bucketname", "objectname");
Log.i("AppendObject", "NextPosition from metadata:" + metadata.getNextPosition());
```

NOTE

- Objects uploaded using **ObsClient.putObject**, referred to as normal objects, can overwrite objects uploaded using **ObsClient.appendObject**, referred to as appendable objects. Data cannot be appended to an appendable object anymore once the object has been overwritten by a normal object.
- When you upload an object for the first time in appendable mode, an exception will be reported (HTTP status code **409**) if a common object with the same name is already present.
- The ETag returned for the append upload is the ETag for the appended content, not that for the entire object.
- Data size in each appendable upload cannot exceed 5 GB, and 10,000 times of appendable uploads can be performed on a single object.
- After an appendable upload is successful, you can use **AppendObjectResult.getNextPosition** or call **ObsClient.getObjectMetadata** to get the start position for next appending.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **AppendObjectRequest.setIsEncodeHeaders(false)** to disable auto encoding.

6.10 Performing a Multipart Copy

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

As a special case of multipart upload, multipart copy implements multipart upload by copying the whole or partial object in a bucket. You can call **ObsClient.copyPart** to copy parts.

 Copyright © Huawei Technologies Co., Ltd.

This example copies object **sourceobjectname** from bucket **sourcebucketname** to bucket **destbucketname** as object **destobjectname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
final String destBucketName = "destbucketname";
final String destObjectKey = "destobjectname";
final String sourceBucketName = "sourcebucketname";
final String sourceObjectKey = "sourceobjectname";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Initialize the thread pool.
ExecutorService executorService = Executors.newFixedThreadPool(20);

// Initiate a multipart upload.
InitiateMultipartUploadRequest request = new InitiateMultipartUploadRequest(destBucketName, destObjectKey);
InitiateMultipartUploadResult result = obsClient.initiateMultipartUpload(request);

final String uploadId = result.getUploadId();
Log.i("CopyPart","\t"+ uploadId + "\n");

// Obtain information about the large object.
ObjectMetadata metadata = obsClient.getObjectMetadata(sourceBucketName, sourceObjectKey);
// Set the part size for copying to 100 MB.
long partSize = 100 * 1024 * 1024L;
long objectSize = metadata.getContentLength();

// Calculate the number of parts to be copied.
long partCount = objectSize % partSize == 0 ? objectSize / partSize : objectSize / partSize + 1;

final List<PartEtag> partEtags = Collections.synchronizedList(new ArrayList<PartEtag>());

// Concurrently copy parts.
for (int i = 0; i < partCount; i++)
{
// Start position for copying
   final long rangeStart = i * partSize;
// End position for copying
   final long rangeEnd = (i + 1 == partCount) ? objectSize - 1 : rangeStart + partSize - 1;
// Part number
   final int partNumber = i + 1;
   executorService.execute(new Runnable()
   {

      @Override
      public void run()
      {
         CopyPartRequest request = new CopyPartRequest();
         request.setUploadId(uploadId);
         request.setSourceBucketName(sourceBucketName);
         request.setSourceObjectKey(sourceObjectKey);
         request.setDestinationBucketName(destBucketName);
         request.setDestinationObjectKey(destObjectKey);
         request.setByteRangeStart(rangeStart);
         request.setByteRangeEnd(rangeEnd);
         request.setPartNumber(partNumber);
         CopyPartResult result;
         try
```

 Copyright © Huawei Technologies Co., Ltd.

```
            {
                result = obsClient.copyPart(request);
                Log.i("CopyPart","Part#" + partNumber + " done\n");
                partEtags.add(new PartEtag(result.getEtag(), result.getPartNumber()));
            }
            catch (ObsException e)
            {
                Log.e("CopyPart", e.getMessage(), e);
            }
        }
    });
}

// Wait until the copy is complete.
executorService.shutdown();
while (!executorService.isTerminated())
{
    try
    {
        executorService.awaitTermination(5, TimeUnit.SECONDS);
    }
    catch (InterruptedException e)
    {
        Log.e("CopyPart", e.getMessage(), e);
    }
}

// Combine parts.
CompleteMultipartUploadRequest completeMultipartUploadRequest =
    new CompleteMultipartUploadRequest(destBucketName, destObjectKey, uploadId, partEtags);
obsClient.completeMultipartUpload(completeMultipartUploadRequest);
```

NOTE

Use the **PartNumber** parameter to specify the part number, the **UploadId** parameter to specify the globally unique ID for the multipart upload, the **CopySource** parameter to specify the information about the source object, and the **CopySourceRange** parameter to specify the byte range to copy.

6.11 Performing a Resumable Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Uploading large files often fails due to poor network conditions or program breakdowns. It is a waste of resources to restart the upload process upon an upload failure, and the restarted upload process may still suffer from the unstable network. To resolve such issues, you can use the API for resumable upload, whose working principle is to divide the to-be-uploaded file into multiple parts and upload them separately. The upload result of each part is recorded in a checkpoint file in real time. Only when all parts are successfully uploaded, the result indicating a successful upload will be returned. Otherwise, an exception is thrown to remind you of calling the API again for re-uploading. Based on the upload status of each part recorded in the checkpoint file, the re-uploading will upload the parts failed to be uploaded previously, instead of uploading all parts. By virtue of this, resources are saved and efficiency is improved.

 Copyright © Huawei Technologies Co., Ltd.

You can call **ObsClient.uploadFile** to perform a resumable upload. The following table describes the parameters involved in this API.

Parameter	Description	Method in OBS Android SDK
bucketName	(Mandatory) Bucket name	UploadFileRequest.setBucketName
objectKey	(Mandatory) Object name	UploadFileRequest.setObjectKey
uploadFile	(Mandatory) Local file to be uploaded	UploadFileRequest.setUploadFile
partSize	Part size, in bytes. The value ranges from 100 KB to 5 GB and defaults to 5 MB.	UploadFileRequest.setPartSize
taskNum	Maximum number of threads that can be concurrently executed for uploading. The default value is **1**.	UploadFileRequest.setTaskNum
enableCheckpoint	Whether to enable the resumable upload mode. The default value is **false**, which indicates that this mode is disabled.	UploadFileRequest.setEnableCheckpoint
isEncodeHeaders	Whether to automatically encode the request header.	UploadFileRequest.setIsEncodeHeaders
checkpointFile	File used to record the upload progress. This parameter is effective only in the resumable upload mode. If the value of this parameter is left blank, the file will be in the same directory as the local file to be uploaded.	UploadFileRequest.setCheckpointFile
objectMetadata	Object properties	UploadFileRequest.setObjectMetadata

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
enableCheckSum	Whether to verify the content of the to-be-uploaded file. This parameter is effective only in the resumable upload mode. The default value is **false,** which indicates that the content will not be verified.	UploadFileRequest.setEnableCheckSum
progressListener	Configure the data transmission listener to obtain upload progresses.	UploadFileRequest.setProgressListener

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

UploadFileRequest request = new UploadFileRequest("bucketname", "objectname");
// Set the large file to be uploaded. localfile is the path of the local file to be uploaded. You need to specify the file name.
request.setUploadFile("localfile");
// Set the maximum number of threads that can be concurrently uploaded.
request.setTaskNum(5);
// Set the part size to 10 MB.
request.setPartSize(10 * 1024 * 1024);
// Enable resumable upload.
request.setEnableCheckpoint(true);
try{
    // Perform a resumable upload.
   CompleteMultipartUploadResult result = obsClient.uploadFile(request);
}catch (ObsException e) {
   // When an exception occurs, you can call the API for resumable upload again to perform re-uploading.
}
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- The API for resumable upload, which is implemented based on **multipart upload**, is an encapsulated and enhanced version of multipart upload.
- This API saves resources and improves efficiency upon the re-upload, and speeds up the upload process by concurrently uploading parts. Because this API is transparent to users, users are free from concerns about internal service details, such as the creation and deletion of checkpoint files, division of objects, and concurrent upload of parts.
- The default value of the **enableCheckpoint** parameter is **false**, which indicates that the resumable upload mode is disabled. In such cases, this API degrades to the simple encapsulation of multipart upload, and no checkpoint file will be generated.
- **checkpointFile** and **enableCheckSum** are effective only when **enableCheckpoint** is **true**.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **UploadFileRequest.setIsEncodeHeaders(false)** to disable auto encoding.
- A resumable upload cannot be paused or canceled.

6.12 Performing a Browser-Based Upload

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Performing a browser-based upload is to upload objects to a specified bucket in HTML form. The maximum size of an object is 5 GB.

You can call **ObsClient.createPostSignature** to generate request parameters for browser-based upload. For details about the code examples, see **PostObjectSample**. You can also perform a browser-based upload as follows:

Step 1 Call **ObsClient.createPostSignature** to generate request parameters for authentication.

Step 2 Prepare an HTML form page.

Step 3 Enter the request parameters in the HTML page.

Step 4 Select a local file and upload it in browser-based mode.

----End

NOTE

There are two request parameters generated:

- **policy**, which corresponds to the **policy** field in the form
- **signature**: corresponds to the **signature** field in the form.

 Copyright © Huawei Technologies Co., Ltd.

The following sample code shows how to generate the parameters in a browser-based upload request.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

PostSignatureRequest request = new PostSignatureRequest();
// Fill in parameters in the form.
Map<String, Object> formParams = new HashMap<String, Object>();
// Set the ACL of the object to public read.
formParams.put("x-obs-acl", "public-read");
// Set the MIME type for the object.
formParams.put("content-type", "text/plain");

request.setFormParams(formParams);
// Set the validity period for the browser-based upload request, in seconds.
request.setExpires(3600);
PostSignatureResponse response = obsClient.createPostSignature(request);

// Obtain the request parameters.
Log.i("CreatePostSignature", "\t" + response.getPolicy());
Log.i("CreatePostSignature", "\t" + response.getSignature());
```

Code of an HTML form example is as follows:

```
<html>
<head>
<meta http-equiv="Content-Type" content="text/html; charset=UTF-8" />
</head>
<body>

<form action="http://bucketname.your-endpoint/" method="post" enctype="multipart/form-data">
Object key
<!-- Object name -->
<input type="text" name="key" value="objectname" />
<p>
ACL
<!-- Object ACL -->
<input type="text" name="x-obs-acl" value="public-read" />
<p>
Content-Type
<!-- Object MIME type -->
<input type="text" name="content-type" value="text/plain" />
<p>
<!-- Base64 code of the policy -->
<input type="hidden" name="policy" value="*** Provide your policy ***" />
<!-- AK -->
<input type="hidden" name="AccessKeyId" value="*** Provide your access key ***"/>
<!-- Signature information -->
<input type="hidden" name="signature" value="*** Provide your signature ***"/>

<input name="file" type="file" />
<input name="submit" value="Upload" type="submit" />
</form>
</body>
</html>
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- Values of **policy** and **signature** in the HTML form are obtained from the returned result of **ObsClient.createPostSignature**.
- You can directly download the HTML form example: **PostDemo**.

 Copyright © Huawei Technologies Co., Ltd.

7 Object Download

7.1 Object Download Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS Android SDK provides abundant APIs for object download in the following modes:

- **Performing a Streaming Download**
- **Performing a Partial Download**
- **Performing a Resumable Download**

You can call **ObsClient.getObject** to download an object.

7.2 Performing a Streaming Download

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
```

 Copyright © Huawei Technologies Co., Ltd.

```
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObsObject obsObject = obsClient.getObject("bucketname", "objectname");

// Obtain the object content.
Log.i("GetObject", "Object content:");
InputStream input = obsObject.getObjectContent();
byte[] b = new byte[1024];
ByteArrayOutputStream bos = new ByteArrayOutputStream();
int len;
while ((len=input.read(b)) != -1){
    bos.write(b, 0, len);
}

Log.i("GetObject", new String(bos.toByteArray()));
bos.close();
input.close();
```

NOTE

- After **ObsClient.getObject** is called, an instance of **ObsObject** will be returned. This instance contains the residing bucket, name, properties, and input streams of the object.
- You can operate the input streams of an object to read and write the object to a local file or to the memory.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. The SDK will decode the information in response headers using URL decoding rules.
- If you do not need the SDK to decode for you, call **GetObjectRequest.setIsEncodeHeaders(false)** to disable auto decoding.
- You can also call **obsObject.getMetadata().getOriginalHeaders()** to obtain information about all original response headers.

NOTICE

Object input streams obtained by **ObsObject.getObjectContent** must be closed explicitly. Otherwise, resource leakage occurs.

7.3 Performing a Partial Download

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

When only partial data of an object is required, you can download data falling within a specific range. If the specified range is from 0 to 1,000, data from byte 0 to byte 1,000, 1,001 bytes in total, are returned. If the specified range is invalid, data of the whole object will be returned. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID
```

 Copyright © Huawei Technologies Co., Ltd.

```
and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
// Set the start position and end position for downloading.
request.setRangeStart(0l);
request.setRangeEnd(1000l);
ObsObject obsObject = obsClient.getObject(request);

// Obtain data.
byte[] buf = new byte[1024];
InputStream in = obsObject.getObjectContent();
for (int n = 0; n != -1; ) {
    n = in.read(buf, 0, buf.length);
}

in.close();
```

NOTE

- If the specified range is invalid (because the start or end position is set to a negative integer or the range is larger than the object length), data of the whole object will be returned.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. The SDK will decode the information in response headers using URL decoding rules.
- If you do not need the SDK to decode for you, call **GetObjectRequest.setIsEncodeHeaders(false)** to disable auto decoding.
- You can also call **obsObject.getMetadata().getOriginalHeaders()** to obtain information about all original response headers.
- This download method also can be used to concurrently download parts of a large object. For details about the sample code, see **ConcurrentDownloadObjectSample**.

7.4 Obtaining Download Progresses

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **GetObjectRequest.setProgressInterval** to configure the data transmission interface to obtain download progresses.

This example downloads **objectname** from **bucketname** and uses **ProgressInterval** to monitor the download progress.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
```

 Copyright © Huawei Technologies Co., Ltd.

```
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
request.setProgressListener(new ProgressListener() {

    @Override
    public void progressChanged(ProgressStatus status) {
        // Obtain the average download rate.
        Log.i("GetObject", "AverageSpeed:" + status.getAverageSpeed());
        // Obtain the download progress in percentage.
        Log.i("GetObject", "TransferPercentage:" + status.getTransferPercentage());
    }
});
// Refresh the upload progress each time 1 MB data is uploaded.
request.setProgressInterval(1024 * 1024L);
ObsObject obsObject = obsClient.getObject(request);

// Obtain the object content.
System.out.println("Object content:");
InputStream input = obsObject.getObjectContent();
byte[] b = new byte[1024];
ByteArrayOutputStream bos = new ByteArrayOutputStream();
int len;
while ((len=input.read(b)) != -1){
    bos.write(b, 0, len);
}

System.out.println(new String(bos.toByteArray()));
bos.close();
input.close();
```

NOTE

- You can obtain the download progress when downloading an object in streaming, partial, or resumable mode.

7.5 Performing a Conditioned Download

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

When downloading an object, you can specify one or more conditions. Only when the conditions are met, the object will be downloaded. Otherwise, an exception will be thrown and the download will fail.

You can set the following conditions:

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
If-Modified-Since	Returns the object if it has been modified since the specified time; otherwise, an error is returned.	GetObjectRequest.setIfModifiedSince
If-Unmodified-Since	Returns the object if it has not been modified since the specified time; otherwise, an error is returned.	GetObjectRequest.setIfUnmodifiedSince
If-Match	Returns the source object if its ETag is the same as the one specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.setIfMatchTag
If-None-Match	Returns the source object if its ETag is different from the one specified by this parameter; otherwise, an exception is thrown.	GetObjectRequest.setIfNoneMatchTag

NOTE

- The ETag of an object is the MD5 check value of the object.
- If a request includes **If-Unmodified-Since** or **If-Match** and the specified condition is not met, **412 Precondition Failed** will be returned.
- If a request includes **If-Modified-Since** or **If-None-Match**, and the specified condition is not met, **304 Not Modified** will be returned.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
request.setRangeStart(0l);
request.setRangeEnd(1000l);

request.setIfModifiedSince(new SimpleDateFormat("yyyy-MM-dd").parse("2016-01-01"));
ObsObject obsObject = obsClient.getObject(request);

obsObject.getObjectContent().close();
```

 Copyright © Huawei Technologies Co., Ltd.

7.6 Rewriting Response Headers

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

When downloading an object, you can rewrite some HTTP/HTTPS response headers. The following table lists rewritable response headers.

Parameter	Description	Method in OBS Android SDK
contentType	Rewrites **Content-Type** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setContentType
contentLanguage	Rewrites **Content-Language** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setContentLanguage
expires	Rewrites **Expires** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setExpires
cacheControl	Rewrites **Cache-Control** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setCacheControl
contentDisposition	Rewrites **Content-Disposition** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setContentDisposition
contentEncoding	Rewrites **Content-Encoding** in HTTP/HTTPS responses.	ObjectRepleaceMetadata.setContentEncoding

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
ObjectRepleaceMetadata replaceMetadata = new ObjectRepleaceMetadata();
replaceMetadata.setContentType("image/jpeg");
request.setReplaceMetadata(replaceMetadata);

ObsObject obsObject = obsClient.getObject(request);
Log.i("GetObject", object.getMetadata().getContentType());

obsObject.getObjectContent().close();
```


Copyright © Huawei Technologies Co., Ltd.

7.7 Obtaining Customized Metadata

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

After an object is successfully downloaded, its customized data is returned. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Upload the object and customize the metadata.
PutObjectRequest request = new PutObjectRequest("bucketname", "objectname");
ObjectMetadata metadata = new ObjectMetadata();
metadata.addUserMetadata("property", "property-value");
request.setMetadata(metadata);
obsClient.putObject(request);
// Download the object and obtain the customized metadata.
GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
ObsObject obsObject = obsClient.getObject(request);
// Get object metadata.
System.out.println(obsObject.getMetadata().getContentType());
System.out.println(obsObject.getMetadata().getUserMetadata("property"));

obsObject.getObjectContent().close();
```

NOTE

- After **ObsClient.getObject** is called, an instance of **ObsObject** will be returned. This instance contains the residing bucket, name, properties, and input streams of the object.
- You can operate the input streams of an object to read and write the object to a local file or to the memory.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. The SDK will decode the information in response headers using URL decoding rules.
- If you do not need the SDK to decode for you, call **GetObjectRequest.setIsEncodeHeaders(false)** to disable auto decoding.
- You can also call **obsObject.getMetadata().getOriginalHeaders()** to obtain information about all original response headers.

Copyright © Huawei Technologies Co., Ltd.

7.8 Downloading an Archive Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Before you can download an Archive object, you must restore it. Archive objects can be restored in either of the following ways.

Option	Description	Value in OBS Android SDK
Expedited restore	Data can be restored within 1 to 5 minutes.	RestoreTierEnum.EXPEDITED
Standard restore	Data can be restored within 3 to 5 hours. This is the default option.	RestoreTierEnum.STANDARD

CAUTION

To extend the validity period of the Archive data restored, you can repeatedly restore the data, but you will be billed for each restore. After a second restore, the validity period of Standard object copies will be extended, and you need to pay for storing these copies during the extended period.

You can call **ObsClient.restoreObject** to restore an Archive object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

RestoreObjectRequest request = new RestoreObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("objectname");
request.setDays(1);
request.setRestoreTier(RestoreTierEnum.EXPEDITED);
obsClient.restoreObject(request);

// Wait for the object to be restored.
Thread.sleep(60 * 6 * 1000);

// Download an object.
```


Copyright © Huawei Technologies Co., Ltd.

```
ObsObject obsObject = obsClient.getObject("bucketname", "objectname");

obsObject.getObjectContent().close();
```

NOTE

- The object specified in **ObsClient.restoreObject** must be in the OBS Archive storage class. Otherwise, an exception will be thrown when you call this API.
- **RestoreObjectRequest.setDays** specifies the retention period of restored objects, ranging from 1 to 30.
- **RestoreObjectRequest.setTier** specifies the restore option, which indicates the time spent on restoring objects.

7.9 Performing a Resumable Download

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Downloading large files often fails due to poor network conditions or program breakdowns. It is a waste of resources to restart the download process upon a download failure, and the restarted download process may still suffer from the unstable network. To resolve such issues, you can use the API for resumable download, whose working principle is to divide the to-be-downloaded file into multiple parts and download them separately. The download result of each part is recorded in a checkpoint file in real time. Only when all parts are successfully downloaded, the result indicating a successful download will be returned. Otherwise, an exception is thrown to remind you of calling the API again for re-downloading. Based on the download status of each part recorded in the checkpoint file, the re-downloading will download the parts failed to be downloaded previously, instead of downloading all parts. By virtue of this, resources are saved and efficiency is improved.

You can call **ObsClient.downloadFile** to perform a resumable download. The following table describes the parameters involved in this API.

Parameter	Description	Method in OBS Android SDK
bucketName	(Mandatory) Bucket name	DownloadFileRequest.setBucketName
objectKey	(Mandatory) Object name	DownloadFileRequest.setObjectKey

Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
downloadFile	Local path to which the object is downloaded. If the parameter is left blank, the downloaded object is saved in the directory where the program is executed.	DownloadFileRequest.setDownloadFile
partSize	Part size, in bytes. The value ranges from 100 KB to 5 GB and defaults to 5 MB.	DownloadFileRequest.setPartSize
taskNum	Maximum number of threads that can be concurrently executed for downloading. The default value is **1**.	DownloadFileRequest.setTaskNum
isEncodeHeaders	Whether to automatically decode the response header.	DownloadFileRequest.setIsEncodeHeaders
enableCheckpoint	Whether to enable the resumable download mode. The default value is **false**, which indicates that this mode is disabled.	DownloadFileRequest.setEnableCheckpoint
checkpointFile	File used to record the download progress. This parameter is effective only in the resumable download mode. If the value of this parameter is left blank, the file will be in the same local directory as the downloaded object.	DownloadFileRequest.setCheckpointFile
versionId	Object version	DownloadFileRequest.setVersionId
ifModifiedSince	Returns the object if it has been modified since the specified time; otherwise, an error is returned.	DownloadFileRequest.setIfModifiedSince
ifUnmodifiedSince	Returns the object if it has not been modified since the specified time; otherwise, an error is returned.	DownloadFileRequest.setIfUnmodifiedSince
ifMatchTag	Returns the source object if its ETag is the same as the one specified by this parameter; otherwise, an exception is thrown.	DownloadFileRequest.setIfMatchTag

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
ifNoneMatchTag	Returns the source object if its ETag is different from the one specified by this parameter; otherwise, an exception is thrown.	DownloadFileRequest.setIfNoneMatchTag
progressListener	Configure the data transmission listener to obtain download progresses.	DownloadFileRequest.setProgressListener

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
DownloadFileRequest request = new DownloadFileRequest("bucketname", "objectname");
// Set the local path to which the object is downloaded.
request.setDownloadFile("localfile");
// Set the maximum number of threads that can be concurrently executed for downloading.
request.setTaskNum(5);
// Set the part size to 10 MB.
request.setPartSize(10 * 1024 * 1024);
// Enable resumable download.
request.setEnableCheckpoint(true);
try{
    // Perform a resumable download.
    DownloadFileResult result = obsClient.downloadFile(request);
}catch (ObsException e) {
// When an exception occurs, you can call the API for resumable download again to perform re-downloading.
}
```

NOTE

- The API for resumable download, which is implemented based on **partial download**, is an encapsulated and enhanced version of partial download.
- This API saves resources and improves efficiency upon the re-download, and speeds up the download process by concurrently downloading parts. Because this API is transparent to users, users are free from concerns about internal service details, such as the creation and deletion of checkpoint files, division of objects, and concurrent download of parts.
- The default value of the **enableCheckpoint** parameter is **false**, which indicates that the resumable download mode is disabled. In such cases, this API degrades to the simple encapsulation of partial download, and no checkpoint file will be generated.
- **checkpointFile** is effective only when **enableCheckpoint** is **true**.
- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. The SDK will decode the information in response headers using URL decoding rules.
- If you do not need the SDK to decode for you, call **DownloadFileRequest.setIsEncodeHeaders(false)** to disable auto decoding.

 Copyright © Huawei Technologies Co., Ltd.

7.10 Processing an Image

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS can be used to process images in a stable, secure, efficient, easy to use, and cost-efficient manner. If the object to be downloaded is an image, you can pass the image processing parameters to process the image, including cutting and resizing it as well as putting a watermark and converting the format.

For more information, see **Image Processing Feature Guide**.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);
GetObjectRequest request = new GetObjectRequest("bucketname", "objectname.jpg");
// Resize and then rotate the image.
request.setImageProcess("image/resize,m_fixed,w_100,h_100/rotate,90");
ObsObject obsObject = obsClient.getObject(request);

obsObject.getObjectContent().close();
```

NOTE

- Use **GetObjectRequest.setImageProcess** to specify the image processing parameters.
- Image processing parameters can be processed in cascading mode. This indicates that multiple commands can be performed on an image in sequence.

Copyright © Huawei Technologies Co., Ltd.

8 Object Management

8.1 Setting Object Properties

You can call **ObsClient.setObjectMetadata** to set object properties, including custom metadata.

In addition to standard HTTP headers, you can also customize metadata. Custom metadata can contain only letters, digits, and hyphens (-).

Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

SetObjectMetadataRequest request = new SetObjectMetadataRequest("bucketname", "objectname");
// Standard HTTP headers of an object
request.setContentType("ContentType");
request.setExpires("Expires");
// Customize metadata.
request.addUserMetadata("property1", "property-value1");

ObjectMetadata metadata = obsClient.setObjectMetadata(request);

Log.i("\t" + metadata.getUserMetadata("property1"));
```

NOTE

- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. If your request headers contain full-width characters, the SDK will URL encode these characters before sending the request. When you use a browser to access the object metadata, the browser automatically decodes the data.
- If you do not need the SDK to decode for you, call **SetObjectMetadataRequest.setIsEncodeHeaders(false)** to disable auto encoding.

 Copyright © Huawei Technologies Co., Ltd.

8.2 Obtaining Object Attributes

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getObjectMetadata** to obtain attributes of an object, including the length, MIME type, and custom metadata. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObjectMetadata metadata = obsClient.getObjectMetadata("bucketname", "objectname");
Log.i("GetObjectMetadata","\t" + metadata.getContentType());
Log.i("GetObjectMetadata","\t" + metadata.getContentLength());
// Obtain custom metadata.
Log.i("GetObjectMetadata","\t" + metadata.getUserMetadata("property"));
// Obtain all original response headers.
Log.i("GetObjectMetadata","\t" + metadata.getOriginalHeaders());
```

NOTE

- Due to HTTP coding restrictions, non-ASCII characters cannot be sent. The SDK will decode the information in response headers using URL decoding rules.
- If you do not need the SDK to decode for you, call **GetObjectMetadataRequest.setIsEncodeHeaders(false)** to disable auto decoding.
- You can also call **metadata.getOriginalHeaders** to obtain information about all original response headers.

8.3 Managing Object ACLs

Access control lists (ACLs) allow resource owners to grant other accounts the permissions to access resources. By default, only the resource owner has full control over resources when a bucket or object is created. That is, the bucket creator has full control over the bucket, and the object uploader has full control over the object. Other accounts do not have the permissions to access resources. If resource owners want to grant other accounts the read and write permissions on resources, they can use ACLs. ACLs grant permissions to accounts. After an account is granted permissions, both the account and its IAM users can access the resources.

For more information, see **ACLs**.

 Copyright © Huawei Technologies Co., Ltd.

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

An object ACL can be configured in any of the following ways:

1. Specify a pre-defined ACL during object upload.
2. Call ObsClient.setObjectAcl to specify a pre-defined ACL.
3. Call ObsClient.setObjectAcl to specify a user-defined ACL.

Specifying a Pre-defined ACL During Object Upload

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

PutObjectRequest request = new PutObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("objectname");
request.setFile(new File("localfile")); // localfile indicates the path of the local file to be uploaded. You need to specify the file name.
// Set the ACL of the object to public read.
request.setAcl(AccessControlList.REST_CANNED_PUBLIC_READ);
obsClient.putObject(request);
```

Setting a Pre-defined ACL for an Object

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set the object ACL to private read and write.
obsClient.setObjectAcl("bucketname", "objectname", AccessControlList.REST_CANNED_PRIVATE);
```

Setting a User-defined Object ACL

Sample code:

 Copyright © Huawei Technologies Co., Ltd.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AccessControlList acl = new AccessControlList();
Owner owner = new Owner();
owner.setId("ownerid");
acl.setOwner(owner);
// Grant the FULL_CONTROL permission to a specified user.
acl.grantPermission(new CanonicalGrantee("userid"), Permission.PERMISSION_FULL_CONTROL);
// Grant the READ permission to all users.
acl.grantPermission(GroupGrantee.ALL_USERS, Permission.PERMISSION_READ);
obsClient.setObjectAcl("bucketname", "objectname", acl);
```

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining an Object ACL

You can call ObsClient.getObjectAcl to obtain the ACL of an object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AccessControlList acl = obsClient.getObjectAcl("bucketname", "objectname");
Log.i("GetObjectAcl", acl);
```

8.4 Listing Objects

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.listObjects** to list objects in a bucket.

The following table describes the parameters involved in this API.

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
bucketName	Bucket name	ListObjectsRequest.setBucketName
prefix	Name prefix that the objects to be listed must contain	ListObjectsRequest.setPrefix
marker	Object name to start with when listing objects in a bucket. All objects are listed in the lexicographical order.	ListObjectsRequest.setMarker
maxKeys	Maximum number of objects listed in the response body. The value ranges from **1** to **1000**. If the value exceeds **1000**, only 1,000 objects are returned.	ListObjectsRequest.setMaxKeys
delimiter	Character used to group object names. If the object name contains the **delimiter** parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, **commonPrefix**. (If a prefix is specified in the request, the prefix must be removed from the object name.) For a parallel file system, if this parameter is not specified, all the content in the directory is recursively listed by default, and subdirectories are also listed. In big data scenarios, parallel file systems usually have deep directory levels and each directory has a large number of files. In such case, you are advised to configure **[delimiter="/"]** to list the content in the current directory, but not list subdirectories, thereby improving the listing efficiency.	ListObjectsRequest.setDelimiter

Listing Objects in Simple Mode

The following sample code shows how to list objects in simple mode. A maximum of 1000 objects can be returned.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/
```

 Copyright © Huawei Technologies Co., Ltd.

```
intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ObjectListing result = obsClient.listObjects("bucketname");
for(ObsObject obsObject : result.getObjects()){
    Log.i("ListObjects", "\t" + obsObject.getObjectKey());
    Log.i("ListObjects","\t" + obsObject.getOwner());
}
```

NOTE

- A maximum of 1000 objects can be listed each time. If a bucket contains more than 1000 objects and **ObjectListing.isTruncated** is **true** in the returned result, not all objects are listed. In such cases, you can use **ObjectListing.getNextMarker** to obtain the start position for next listing.
- If you want to obtain all objects in a specified bucket, you can use the paging mode for listing objects.

Listing Objects by Specifying the Number

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
// Specify the number of objects to be listed to 100.
request.setMaxKeys(100);
ObjectListing result = obsClient.listObjects(request);
for(ObsObject obsObject : result.getObjects()){
    Log.i("ListObjects","\t" + obsObject.getObjectKey());
    Log.i("ListObjects","\t" + obsObject.getOwner());
}
```

Listing Objects by Specifying a Prefix

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
// Set the number to 100 and the prefix to prefix.
request.setMaxKeys(100);
```

 Copyright © Huawei Technologies Co., Ltd.

```
request.setPrefix("prefix");
ObjectListing result = obsClient.listObjects(request);
for(ObsObject obsObject : result.getObjects()){
    Log.i("ListObjects","\t" + obsObject.getObjectKey());
    Log.i("ListObjects","\t" + obsObject.getOwner());
}
```

Listing Objects by Specifying the Start Position

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
// List 100 objects following test in lexicographic order.
request.setMaxKeys(100);
request.setMarker("test");
ObjectListing result = obsClient.listObjects(request);
for(ObsObject obsObject : result.getObjects()){
    Log.i("ListObjects","\t" + obsObject.getObjectKey());
    Log.i("ListObjects","\t" + obsObject.getOwner());
}
```

Listing All Objects in Paging Mode

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
// Set the number of objects displayed per page to 100.
request.setMaxKeys(100);

ObjectListing result;
do{
    result = obsClient.listObjects(request);
    for(ObsObject obsObject : result.getObjects()){
        Log.i("ListObjects","\t" + obsObject.getObjectKey());
        Log.i("ListObjects","\t" + obsObject.getOwner());
    }

    request.setMarker(result.getNextMarker());
}while(result.isTruncated());
```

 Copyright © Huawei Technologies Co., Ltd.

Listing All Objects in a Folder

There is no folder concept in OBS. All elements in buckets are objects. Folders are actually objects whose sizes are 0 and whose names end with a slash (/). When you set a folder name as the prefix, objects in this folder will be listed. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
// Set the prefix of objects in the folder to dir/.
request.setPrefix("dir/");
request.setMaxKeys(1000);

ObjectListing result;

do{
    result = obsClient.listObjects(request);
    for (ObsObject obsObject : result.getObjects())
    {
        Log.i("ListObjects","\t" + obsObject.getObjectKey());
        Log.i("ListObjects","\t" + obsObject.getOwner());
    }
    request.setMarker(result.getNextMarker());
}while(result.isTruncated());
```

Listing All Objects According to Folders in a Bucket

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListObjectsRequest request = new ListObjectsRequest("bucketname");
request.setMaxKeys(1000);
// Set folder isolators to slashes.
request.setDelimiter("/");
ObjectListing result = obsClient.listObjects(request);
Log.i("ListObjects", "Objects in the root directory:");
for(ObsObject obsObject : result.getObjects()){
    Log.i("ListObjects","\t" + obsObject.getObjectKey());
    Log.i("ListObjects","\t" + obsObject.getOwner());
}
listObjectsByPrefix(obsClient, request, result);
```

The following is the sample code of the **listObjectsByPrefix** function, which is used to recursively list objects in sub-folders.

 Copyright © Huawei Technologies Co., Ltd.

```
static void listObjectsByPrefix(ObsClient obsClient, ListObjectsRequest request, ObjectListing result) throws
ObsException
{
    for(String prefix : result.getCommonPrefixes()){
        Log.i("ListObjects", "Objects in folder [" + prefix + "]:");
        request.setPrefix(prefix);
        result  = obsClient.listObjects(request);
        for(ObsObject obsObject : result.getObjects()){
            Log.i("ListObjects","\t" + obsObject.getObjectKey());
            Log.i("ListObjects","\t" + obsObject.getOwner());
        }
        listObjectsByPrefix(obsClient, request, result);
    }
}
```

NOTE

- The sample code does not apply to scenarios where the number of objects in a folder exceeds 1000.
- Because objects and sub-folders in a folder are to be listed and all the objects end with a slash (/), **delimiter** is always a slash (/).
- In the returned result of each recursion, **ObjectListing.getObjects** includes the objects in the folder and **ObjectListing.getCommonPrefixes** includes the sub-folders in the folder.

8.5 Deleting Objects

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

NOTE

Exercise caution when performing this operation. If the versioning function is disabled for the bucket where the object is located, the object cannot be restored after being deleted.

Deleting a Single Object

You can call **ObsClient.deleteObject** to delete a single object. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
obsClient.deleteObject("bucketname", "objectname");
```

Deleting Objects in a Batch

You can call **ObsClient.deleteObjects** to delete objects in a batch.

 Copyright © Huawei Technologies Co., Ltd.

A maximum of 1000 objects can be deleted each time. Two response modes are supported: **verbose** (detailed) and **quiet** (brief).

- In verbose mode (default mode), the returned response includes the deletion result of each requested object.
- In quiet mode, the returned response includes only results of objects failed to be deleted.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListVersionsRequest request = new ListVersionsRequest("bucketname");
// Delete 100 objects at a time.
request.setMaxKeys(100);
ListVersionsResult result;
do {
    result = obsClient.listVersions(request);

    DeleteObjectsRequest deleteRequest = new DeleteObjectsRequest("bucketname");

    for(VersionOrDeleteMarker v  : result.getVersions()) {
        deleteRequest.addKeyAndVersion(v.getKey(), v.getVersionId());
    }

    DeleteObjectsResult deleteResult = obsClient.deleteObjects(deleteRequest);
    // Obtain the successfully deleted objects.
    Log.i("DeletesObjects",deleteResult.getDeletedObjectResults());
    // Obtain the list of objects failed to be deleted.
    Log.i("DeletesObjects", deleteResult.getErrorResults());

    request.setKeyMarker(deleteResult.getNextKeyMarker());
    request.setVersionIdMarker(deleteResult.getNextVersionIdMarker());
}while(result.isTruncated());
```

8.6 Copying an Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

The object copy operation can create a copy for an existing object in OBS.

You can call **ObsClient.copyObject** to copy an object. When copying an object, you can rewrite properties and ACL for it, as well as set restriction conditions.

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- If the source object to be copied is in the Archive storage class, you must restore it first.

Copying an Object in Simple Mode

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

CopyObjectResult result = obsClient.copyObject("sourcebucketname", "sourceobjectname",
"destbucketname", "destobjectname");
Log.i("CopyObject","\t" + result.getEtag());
```

Rewriting Object Properties

The following sample code shows how to rewrite object properties.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

CopyObjectRequest request = new CopyObjectRequest("sourcebucketname", "sourceobjectname",
"destbucketname", "destobjectname");
// Rewrite object properties.
request.setReplaceMetadata(true);
ObjectMetadata newObjectMetadata = new ObjectMetadata();
newObjectMetadata.setContentType("image/jpeg");
newObjectMetadata.addUserMetadata("property", "property-value");
newObjectMetadata.setObjectStorageClass(StorageClassEnum.WARM);
request.setNewObjectMetadata(newObjectMetadata);
CopyObjectResult result = obsClient.copyObject(request);
Log.i("CopyObject","\t" + result.getEtag());
```

NOTE

CopyObjectRequest.setReplaceMetadata and **CopyObjectRequest.setNewObjectMetadata** must be used together.

Copying an Object by Specifying Conditions

When copying an object, you can specify one or more restriction conditions. If the conditions are met, the object will be copied. Otherwise, an exception will be thrown and the copy will fail.

You can set the following conditions:

 Copyright © Huawei Technologies Co., Ltd.

Parameter	Description	Method in OBS Android SDK
Copy-Source-If-Modified-Since	Copies the source object if it has been modified since the specified time; otherwise, an exception is thrown.	CopyObjectRequest.setIfModifiedSince
Copy-Source-If-Unmodified-Since	Copies the source object if it has not been modified since the specified time; otherwise, an exception is thrown.	CopyObjectRequest.setIfUnmodifiedSince
Copy-Source-If-Match	Copies the source object if its ETag is the same as the one specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.setIfMatchTag
Copy-Source-If-None-Match	Copies the source object if its ETag is different from the one specified by this parameter; otherwise, an exception is thrown.	CopyObjectRequest.setIfNoneMatchTag

NOTE

- The ETag of the source object is the MD5 check value of the source object.
- If **Copy-Source-If-Unmodified-Since**, **Copy-Source-If-Match**, **Copy-Source-If-Modified-Since**, or **Copy-Source-If-None-Match** is included and its specified condition is not met, an exception, whose HTTP status code is **412 Precondition Failed**, will be thrown.
- **Copy-Source-If-Modified-Since** and **Copy-Source-If-None-Match** can be used together, and so do **Copy-Source-If-Unmodified-Since** and **Copy-Source-If-Match**.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

CopyObjectRequest request = new CopyObjectRequest("sourcebucketname", "sourceobjectname", "destbucketname", "destobjectname");

request.setIfModifiedSince(new SimpleDateFormat("yyyy-MM-dd").parse("2016-01-01"));
request.setIfNoneMatchTag("none-match-etag");
```

 Copyright © Huawei Technologies Co., Ltd.

```
CopyObjectResult result = obsClient.copyObject(request);
Log.i("CopyObject","\t" + result.getEtag());
```

Rewriting an Object ACL

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

CopyObjectRequest request = new CopyObjectRequest("sourcebucketname", "sourceobjectname", "destbucketname", "destobjectname");

// Rewrite the object ACL to public read during the copy.
request.setAcl(AccessControlList.REST_CANNED_PUBLIC_READ);
CopyObjectResult result = obsClient.copyObject(request);
Log.i("CopyObject","\t" + result.getEtag());
```

 Copyright © Huawei Technologies Co., Ltd.

9 Temporarily Authorized Access

9.1 Using a Temporary URL for Authorized Access

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

ObsClient allows you to create a URL whose **Query** parameters are carried with authentication information by specifying the AK and SK, HTTP method, and request parameters. You can provide other users with this URL for temporary access. When generating a URL, you need to specify the validity period of the URL to restrict the access duration of visitors.

If you want to grant other users the permission to perform other operations on buckets or objects (for example, upload or download objects), generate a URL with the corresponding request (for example, to upload an object using the URL that generates the PUT request) and provide the URL for other users.

The following table lists operations can be performed through a signed URL.

Operation	HTTP Request Method (Value in OBS Android SDK)	Special Operator (Value in OBS Android SDK)	Bucket Name Required	Object Name Required
PUT Bucket	HttpMethodEnum.PUT	N/A	Yes	No
GET Buckets	HttpMethodEnum.GET	N/A	No	No
DELETE Bucket	HttpMethodEnum.DELETE	N/A	Yes	No

 Copyright © Huawei Technologies Co., Ltd.

Operation	HTTP Request Method (Value in OBS Android SDK)	Special Operator (Value in OBS Android SDK)	Bucket Name Required	Object Name Required
GET Objects	HttpMethodEnum.GET	N/A	Yes	No
GET Object versions	HttpMethodEnum.GET	SpecialParamEnum.VERSIONS	Yes	No
List Multipart uploads	HttpMethodEnum.GET	SpecialParamEnum.UPLOADS	Yes	No
Obtain Bucket Metadata	HttpMethodEnum.HEAD	N/A	Yes	No
GET Bucket location	HttpMethodEnum.GET	SpecialParamEnum.LOCATION	Yes	No
GET Bucket storageinfo	HttpMethodEnum.GET	SpecialParamEnum.STORAGEINFO	Yes	No
PUT Bucket quota	HttpMethodEnum.PUT	SpecialParamEnum.QUOTA	Yes	No
GET Bucket quota	HttpMethodEnum.GET	SpecialParamEnum.QUOTA	Yes	No
Set Bucket storagePolicy	HttpMethodEnum.PUT	SpecialParamEnum.STORAGEPOLICY	Yes	No
GET Bucket storagePolicy	HttpMethodEnum.GET	SpecialParamEnum.STORAGEPOLICY	Yes	No
Configure Bucket ACL	HttpMethodEnum.PUT	SpecialParamEnum.ACL	Yes	No
Obtain Bucket ACL	HttpMethodEnum.GET	SpecialParamEnum.ACL	Yes	No
PUT Bucket logging	HttpMethodEnum.PUT	SpecialParamEnum.LOGGING	Yes	No
GET Bucket logging	HttpMethodEnum.GET	SpecialParamEnum.LOGGING	Yes	No
PUT Bucket policy	HttpMethodEnum.PUT	SpecialParamEnum.POLICY	Yes	No
GET Bucket policy	HttpMethodEnum.GET	SpecialParamEnum.POLICY	Yes	No

 Copyright © Huawei Technologies Co., Ltd.

Operation	HTTP Request Method (Value in OBS Android SDK)	Special Operator (Value in OBS Android SDK)	Bucket Name Required	Object Name Required
DELETE Bucket policy	HttpMethodEnum.DELETE	SpecialParamEnum.POLICY	Yes	No
PUT Bucket lifecycle	HttpMethodEnum.PUT	SpecialParamEnum.LIFECYCLE	Yes	No
GET Bucket lifecycle	HttpMethodEnum.GET	SpecialParamEnum.LIFECYCLE	Yes	No
DELETE Bucket lifecycle	HttpMethodEnum.DELETE	SpecialParamEnum.LIFECYCLE	Yes	No
PUT Bucket website	HttpMethodEnum.PUT	SpecialParamEnum.WEBSITE	Yes	No
GET Bucket website	HttpMethodEnum.GET	SpecialParamEnum.WEBSITE	Yes	No
DELETE Bucket website	HttpMethodEnum.DELETE	SpecialParamEnum.WEBSITE	Yes	No
PUT Bucket versioning	HttpMethodEnum.PUT	SpecialParamEnum.VERSIONING	Yes	No
GET Bucket versioning	HttpMethodEnum.GET	SpecialParamEnum.VERSIONING	Yes	No
PUT Bucket cors	HttpMethodEnum.PUT	SpecialParamEnum.CORS	Yes	No
GET Bucket cors	HttpMethodEnum.GET	SpecialParamEnum.CORS	Yes	No
DELETE Bucket cors	HttpMethodEnum.DELETE	SpecialParamEnum.CORS	Yes	No
PUT Bucket tagging	HttpMethodEnum.PUT	SpecialParamEnum.TAGGING	Yes	No
GET Bucket tagging	HttpMethodEnum.GET	SpecialParamEnum.TAGGING	Yes	No
DELETE Bucket tagging	HttpMethodEnum.DELETE	SpecialParamEnum.TAGGING	Yes	No
PUT Object	HttpMethodEnum.PUT	N/A	Yes	Yes

 Copyright © Huawei Technologies Co., Ltd.

Operation	HTTP Request Method (Value in OBS Android SDK)	Special Operator (Value in OBS Android SDK)	Bucket Name Required	Object Name Required
Append Object	HttpMethodEnum.POST	SpecialParamEnum.APPEND	Yes	Yes
GET Object	HttpMethodEnum.GET	N/A	Yes	Yes
PUT Object - Copy	HttpMethodEnum.PUT	N/A	Yes	Yes
DELETE Object	HttpMethodEnum.DELETE	N/A	Yes	Yes
DELETE Objects	HttpMethodEnum.POST	SpecialParamEnum.DELETE	Yes	Yes
Obtain Object Metadata	HttpMethodEnum.HEAD	N/A	Yes	Yes
Configure Object ACL	HttpMethodEnum.PUT	SpecialParamEnum.ACL	Yes	Yes
Obtain Object ACL	HttpMethodEnum.GET	SpecialParamEnum.ACL	Yes	Yes
Initiate Multipart Upload	HttpMethodEnum.POST	SpecialParamEnum.UPLOADS	Yes	Yes
PUT Part	HttpMethodEnum.PUT	N/A	Yes	Yes
PUT Part - Copy	HttpMethodEnum.PUT	N/A	Yes	Yes
List Parts	HttpMethodEnum.GET	N/A	Yes	Yes
Complete Multipart Upload	HttpMethodEnum.POST	N/A	Yes	Yes
DELETE Multipart upload	HttpMethodEnum.DELETE	N/A	Yes	Yes
POST Object restore	HttpMethodEnum.POST	SpecialParamEnum.RESTORE	Yes	Yes

 Copyright © Huawei Technologies Co., Ltd.

To access OBS using a temporary URL generated by the OBS Android SDK, perform the following steps:

Step 1 Call **ObsClient.createTemporarySignature** to generate a signed URL.

Step 2 Use any HTTP library to make an HTTP/HTTPS request to OBS.

----End

CAUTION

If a CORS or signature mismatch error occurs, refer to the following steps to troubleshoot the issue:

1. If CORS has not been configured, you need to first configure CORS rules on the console. For details, see **Configuring CORS**.
2. If the signatures do not match, check whether signature parameters are correct by referring to **Authentication of Signature in a URL**. For example, during an object upload, the backend uses **Content-Type** to calculate the signature and generate an authorized URL, but if **Content-Type** is not set or set wrongly when the frontend uses the authorized URL, there will be a CORS error. To address this issue, ensure that **Content-Type** fields at the frontend and backend are consistent.

The following content provides examples of accessing OBS using a temporary URL, including bucket creation, as well as object upload, download, listing, and deletion.

Creating a Bucket

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600L;

TemporarySignatureRequest request = new TemporarySignatureRequest(HttpMethodEnum.PUT, expireSeconds);
request.setBucketName("bucketname");
TemporarySignatureResponse response = obsClient.createTemporarySignature(request);
Log.i("CreateTemporarySignature", "Creating bucket using temporary signature url:");
Log.i("CreateTemporarySignature", "\t" + response.getSignedUrl());

Request.Builder builder = new Request.Builder();
for (Map.Entry<String, String> entry : response.getActualSignedRequestHeaders().entrySet()) {
    builder.header(entry.getKey(), entry.getValue());
}
// Make a PUT request to create a bucket.
String location = "your bucket location";
Request httpRequest = builder.url(response.getSignedUrl()).put(RequestBody.create(null, "<CreateBucketConfiguration><LocationConstraint>" + location + "</LocationConstraint></CreateBucketConfiguration>".getBytes())).build();
OkHttpClient httpClient = new OkHttpClient.Builder().followRedirects(false).retryOnConnectionFailure(false)
```

 Copyright © Huawei Technologies Co., Ltd.

```
            .cache(null).build();

Call c = httpClient.newCall(httpRequest);
Response res = c.execute();
Log.i("CreateTemporarySignature", "\tStatus:" + res.code());
if (res.body() != null) {
    Log.i("CreateTemporarySignature", "\tContent:" + res.body().string() + "\n");
}
res.close();
```

Uploading an Object

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600L;

Map<String, String> headers = new HashMap<String, String>();
String contentType = "text/plain";
headers.put("Content-Type", contentType);

TemporarySignatureRequest request = new TemporarySignatureRequest(HttpMethodEnum.PUT, expireSeconds);
request.setBucketName("bucketname");
request.setObjectKey("objectname");
request.setHeaders(headers);

TemporarySignatureResponse response = obsClient.createTemporarySignature(request);

Log.i("CreateTemporarySignature", "Creating object using temporary signature url:");
Log.i("CreateTemporarySignature", "\t" + response.getSignedUrl());
Request.Builder builder = new Request.Builder();
for (Map.Entry<String, String> entry : response.getActualSignedRequestHeaders().entrySet()) {
    builder.header(entry.getKey(), entry.getValue());
}

//Make a PUT request to upload an object.
Request httpRequest =
builder.url(response.getSignedUrl()).put(RequestBody.create(MediaType.parse(contentType), "Hello OBS".getBytes("UTF-8"))).build();
OkHttpClient httpClient = new
OkHttpClient.Builder().followRedirects(false).retryOnConnectionFailure(false)
            .cache(null).build();

Call c = httpClient.newCall(httpRequest);
Response res = c.execute();
Log.i("CreateTemporarySignature", "\tStatus:" + res.code());
if (res.body() != null) {
    Log.i("CreateTemporarySignature", "\tContent:" + res.body().string() + "\n");
}
res.close();
```

Downloading an Object

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
```

 Copyright © Huawei Technologies Co., Ltd.

```
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600L;


TemporarySignatureRequest request = new TemporarySignatureRequest(HttpMethodEnum.GET,
expireSeconds);
request.setBucketName("bucketname");
request.setObjectKey("objectname");

TemporarySignatureResponse response = obsClient.createTemporarySignature(request);

Log.i("CreateTemporarySignature", "Getting object using temporary signature url:");
Log.i("CreateTemporarySignature", "\t" + response.getSignedUrl());
Request.Builder builder = new Request.Builder();
for (Map.Entry<String, String> entry : response.getActualSignedRequestHeaders().entrySet()) {
    builder.header(entry.getKey(), entry.getValue());
}

//Make a GET request to download an object.
Request httpRequest = builder.url(response.getSignedUrl()).get().build();
OkHttpClient httpClient = new
OkHttpClient.Builder().followRedirects(false).retryOnConnectionFailure(false)
        .cache(null).build();

Call c = httpClient.newCall(httpRequest);
Response res = c.execute();
Log.i("CreateTemporarySignature", "\tStatus:" + res.code());
if (res.body() != null) {
    Log.i("CreateTemporarySignature", "\tContent:" + res.body().string() + "\n");
}
res.close();
```

Listing Objects

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600L;


TemporarySignatureRequest request = new TemporarySignatureRequest(HttpMethodEnum.GET,
expireSeconds);
request.setBucketName("bucketname");

TemporarySignatureResponse response = obsClient.createTemporarySignature(request);

Log.i("CreateTemporarySignature", "Getting object list using temporary signature url:");
Log.i("CreateTemporarySignature", "\t" + response.getSignedUrl());
Request.Builder builder = new Request.Builder();
for (Map.Entry<String, String> entry : response.getActualSignedRequestHeaders().entrySet()) {
    builder.header(entry.getKey(), entry.getValue());
}

//Make a GET request to obtain the object list.
Request httpRequest = builder.url(response.getSignedUrl()).get().build();
```

 Copyright © Huawei Technologies Co., Ltd.

```
OkHttpClient httpClient = new
OkHttpClient.Builder().followRedirects(false).retryOnConnectionFailure(false)
        .cache(null).build();

Call c = httpClient.newCall(httpRequest);
Response res = c.execute();
Log.i("CreateTemporarySignature", "\tStatus:" + res.code());
if (res.body() != null) {
    Log.i("CreateTemporarySignature", "\tContent:" + res.body().string() + "\n");
}
res.close();
```

Deleting an Object

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
// Specify the validity period of the URL to 3600 seconds.
long expireSeconds = 3600L;


TemporarySignatureRequest request = new TemporarySignatureRequest(HttpMethodEnum.DELETE, expireSeconds);
request.setBucketName("bucketname");
request.setObjectKey("objectname");

TemporarySignatureResponse response = obsClient.createTemporarySignature(request);

Log.i("CreateTemporarySignature", "Deleting object using temporary signature url:");
Log.i("CreateTemporarySignature", "\t" + response.getSignedUrl());
Request.Builder builder = new Request.Builder();
for (Map.Entry<String, String> entry : response.getActualSignedRequestHeaders().entrySet()) {
    builder.header(entry.getKey(), entry.getValue());
}

//Make a DELETE request to delete an object.
Request httpRequest = builder.url(response.getSignedUrl()).delete().build();
OkHttpClient httpClient = new
OkHttpClient.Builder().followRedirects(false).retryOnConnectionFailure(false)
        .cache(null).build();

Call c = httpClient.newCall(httpRequest);
Response res = c.execute();
Log.i("CreateTemporarySignature", "\tStatus:" + res.code());
if (res.body() != null) {
    Log.i("CreateTemporarySignature", "\tContent:" + res.body().string() + "\n");
}
res.close();
```

NOTE

HttpMethodEnum is an enumeration function defined in OBS Android SDK, whose value indicates the request method types.

 Copyright © Huawei Technologies Co., Ltd.

10 Versioning Management

10.1 Versioning Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can use versioning to store multiple versions of an object in a bucket.

When versioning is enabled for a bucket, OBS keeps multiple versions of an object in the bucket, allowing you to easily retrieve and restore historical versions or recover data in the event of accidental changes or application failures.

By default, versioning is disabled for new OBS buckets. In this case, if a newly uploaded object is using the name of the previously uploaded one, the new object will overwrite the previous one.

For details, see **Versioning**.

10.2 Setting Versioning Status for a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.setBucketVersioning** to set the versioning status for a bucket. OBS supports two versioning statuses.

 Copyright © Huawei Technologies Co., Ltd.

Versioning Status	Description	Value in OBS Android SDK
Enabled	1. OBS creates a unique version ID for each uploaded object. Namesake objects are not overwritten and are distinguished by their own version IDs. 2. Objects can be downloaded by specifying the version ID. By default, the object of the latest version is downloaded if no version ID is specified. 3. Objects can be deleted by specifying the version ID. If an object is deleted with no version ID specified, the object will generate a delete marker with a unique version ID but is not physically deleted. 4. The latest objects in a bucket are returned by default after **ObsClient.listObjects** is called. You can call **ObsClient.listVersions** to list a bucket's objects with all version IDs. 5. Except for delete markers, storage space occupied by objects with all version IDs is billed.	VersioningStatusEnum.ENABLED
Suspended	1. Noncurrent object versions are not affected. 2. OBS creates version ID **null** to an uploaded object and the object will be overwritten after a namesake one is uploaded. 3. Objects can be downloaded by specifying the version ID. By default, the object of the latest version is downloaded if no version ID is specified. 4. Objects can be deleted by specifying version IDs. If an object is deleted with no version ID specified, the object is only attached with a delete marker whose version ID is **null**. Objects with version ID **null** are physically deleted. 5. Except for delete markers, storage space occupied by objects with all version IDs is billed.	VersioningStatusEnum.SUSPENDED

 Copyright © Huawei Technologies Co., Ltd.

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Enable versioning.
obsClient.setBucketVersioning("bucketname", new
BucketVersioningConfiguration(VersioningStatusEnum.ENABLED));

// Suspend versioning.
obsClient.setBucketVersioning("bucketname", new
BucketVersioningConfiguration(VersioningStatusEnum.SUSPENDED));
```

10.3 Viewing Versioning Status of a Bucket

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketVersioning** to view the versioning status of a bucket.

This example obtains the versioning status of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketVersioningConfiguration status = obsClient.getBucketVersioning("bucketname");
Log.i("GetBucketVersioning", "\t" + status.getVersioningStatus());
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

10.4 Obtaining a Versioning Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getObject** to obtain an object version by specifying the version ID (**versionId**).

This example downloads object **objectname** from bucket **bucketname** by specifying **VersionId**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set versionId to obtain a versioning object.
ObsObject obsObject = obsClient.getObject("bucketname", "objectname", "versionid");
obsObject.getObjectContent().close();
```

NOTE

- If version ID is left blank, the latest version of the object will be downloaded.

10.5 Copying a Versioning Object

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.copyObject** to copy an object version by specifying the version ID (**versionId**).

This example specifies **versionId** to copy **sourceobjectname** of the specified version from **sourcebucketname** to **destbucketname** as **destobjectname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

 Copyright © Huawei Technologies Co., Ltd.

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

CopyObjectRequest request = new CopyObjectRequest();
request.setSourceBucketName("sourebucketname");
request.setSourceObjectKey("sourceobjectname");
// Set the version ID of the object to be copied.
request.setVersionId("versionid");
request.setDestinationBucketName("destbucketname");
request.setDestinationObjectKey("destobjectname");
obsClient.copyObject(request);
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

10.6 Restoring a Specific Archive Object Version

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.restoreObject** to restore an Archive object version by specifying **versionId**.

This example specifies **versionId** to restore Archive object **destobjectname** in **destbucketname** as a Standard object.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

RestoreObjectRequest request = new RestoreObjectRequest("bucketname", "objectname", 1);
// Restore a versioned object at an expedited speed.
request.setRestoreTier(RestoreTierEnum.EXPEDITED);
request.setVersionId("versionid");
obsClient.restoreObject(request);
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

10.7 Listing Versioning Objects

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.listVersions** to list versioning objects.

The following table describes the parameters involved in this API.

Parameter	Description
bucketName	Bucket name
prefix	Name prefix that the objects to be listed must contain
keyMarker	Object name to start with when listing versioning objects in a bucket. All versioning objects whose names follow this parameter are listed in the lexicographical order.
maxKeys	Maximum number of versioning objects listed. The value ranges from 1 to 1000. If the value is not in this range, 1000 versioning objects are listed by default.
delimiter	Character used to group object names. If the object name contains the **delimiter** parameter, the character string from the first character to the first delimiter in the object name is grouped under a single result element, **commonPrefix**. (If a prefix is specified in the request, the prefix must be removed from the object name.)
versionIdMarker	All versioning objects are listed in the lexicographical order by object name and version ID. This parameter must be used together with **keyMarker**.

NOTE

- If the value of **versionIdMarker** is not a version ID specified by **keyMarker**, **versionIdMarker** is ineffective.
- The returned result of **ObsClient.listVersions** includes the versioning objects and delete markers.

Listing Versioning Objects in Simple Mode

The following sample code shows how to list versioning objects in simple mode. A maximum of 1000 versioning objects can be returned.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

 Copyright © Huawei Technologies Co., Ltd.

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListVersionsResult result = obsClient.listVersions("bucketname");

for(VersionOrDeleteMarker v : result.getVersions()){
    Log.i("ListVersions", "\t" + v.getKey());
    Log.i("ListVersions","\t" + v.getOwner());
    Log.i("ListVersions","\t" + v.isDeleteMarker());
}
```

NOTE

- A maximum of 1000 versioning objects can be listed each time. If a bucket contains more than 1000 objects and **ListVersionsResult.isTruncated** is **true** in the returned result, not all versioning objects are listed. In such cases, you can use **ListVersionsResult.getNextKeyMarker** and **ListVersionsResult.getNextVersionIdMarker** to obtain the start position for next listing.
- If you want to obtain all versioning objects in a specified bucket, you can use the paging mode for listing objects.

Listing Versioning Objects by Specifying the Number

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListVersionsResult result = obsClient.listVersions("bucketname", 100);
for(VersionOrDeleteMarker v : result.getVersions()){
    Log.i("ListVersions","\t" + v.getKey());
    Log.i("ListVersions","\t" + v.getOwner());
    Log.i("ListVersions","\t" + v.isDeleteMarker());
}
```

Listing Versioning Objects by Specifying a Prefix

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
```

```
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// List 100 objects whose name prefix is prefix.
ListVersionsRequest request = new ListVersionsRequest ("bucketname", 100);
request.setPrefix("prefix");
ListVersionsResult result = obsClient.listVersions(request);
for(VersionOrDeleteMarker v : result.getVersions()){
    Log.i("ListVersions","\t" + v.getKey());
    Log.i("ListVersions","\t" + v.getOwner());
    Log.i("ListVersions","\t" + v.isDeleteMarker());
}
```

Listing Versioning Objects by Specifying the Start Position

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// List 100 versioning objects whose names following test in lexicographic order.
ListVersionsRequest request = new ListVersionsRequest ("bucketname", 100);
request.setKeyMarker("test");
ListVersionsResult result = obsClient.listVersions(request);

for(VersionOrDeleteMarker v : result.getVersions()){
    Log.i("ListVersions","\t" + v.getKey());
    Log.i("ListVersions","\t" + v.getOwner());
    Log.i("ListVersions","\t" + v.isDeleteMarker());
}
```

Listing All Versioning Objects in Paging Mode

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListVersionsResult result;
ListVersionsRequest request = new ListVersionsRequest ("bucketname", 100);
do{
    result = obsClient.listVersions(request);
    for(VersionOrDeleteMarker v : result.getVersions()){
        Log.i("ListVersions","\t" + v.getKey());
        Log.i("ListVersions","\t" + v.getOwner());
        Log.i("ListVersions","\t" + v.isDeleteMarker());
    }
    request.setKeyMarker(result.getNextKeyMarker());
    request.setVersionIdMarker(result.getNextVersionIdMarker());
}while(result.isTruncated());
```

 Copyright © Huawei Technologies Co., Ltd.

Listing All Versioning Objects in a Folder

There is no folder concept in OBS. All elements in buckets are objects. Folders are actually objects whose sizes are 0 and whose names end with a slash (/). When you set a folder name as the prefix, objects in this folder will be listed. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

ListVersionsResult result;
ListVersionsRequest request = new ListVersionsRequest ("bucketname", 100);
// Set the prefix of objects in the folder to dir/.
request.setPrefix("dir/");
do{
    result = obsClient.listVersions(request);
    for(VersionOrDeleteMarker v : result.getVersions()){
        Log.i("ListVersions","\t" + v.getKey());
        Log.i("ListVersions","\t" + v.getOwner());
        Log.i("ListVersions","\t" + v.isDeleteMarker());
    }
    request.setKeyMarker(result.getNextKeyMarker());
    request.setVersionIdMarker(result.getNextVersionIdMarker());
}while(result.isTruncated());
```

Listing All Versioning Objects According to Folders in a Bucket

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
ListVersionsRequest request = new ListVersionsRequest ("bucketname", 1000);
request.setDelimiter("/");
ListVersionsResult result = obsClient.listVersions(request);
Log.i("ListVersions", "Objects in the root directory:");
for(VersionOrDeleteMarker v : result.getVersions()){
    Log.i("ListVersions","\t" + v.getKey());
    Log.i("ListVersions","\t" + v.getOwner());
    Log.i("ListVersions","\t" + v.isDeleteMarker());
}

listVersionsByPrefix(obsClient, result);
```

The following is the sample code of the **listVersionsByPrefix** function, which is used to recursively list objects in sub-folders.

```
static void listVersionsByPrefix(ObsClient obsClient, ListVersionsResult result) throws ObsException{
    for(String prefix : result.getCommonPrefixes()){
```

 Copyright © Huawei Technologies Co., Ltd.

```
        Log.i("ListVersions", "Objects in folder [" + prefix + "]:");
        ListVersionsRequest request = new ListVersionsRequest ("bucketname", 1000);
        request.setDelimiter("/");
        request.setPrefix(prefix)
        result = obsClient.listVersions(request);
        for(VersionOrDeleteMarker v : result.getVersions()){
            Log.i("ListVersions","\t" + v.getKey());
            Log.i("ListVersions","\t" + v.getOwner());
            Log.i("ListVersions","\t" + v.isDeleteMarker());
        }
        listVersionsByPrefix(obsClient, result);
    }
}
```

NOTE

- The previous sample code does not include scenarios where the number of objects in a folder exceeds 1000.
- Because objects and sub-folders in a folder are to be listed and all the objects end with a slash (/), **delimiter** is always a slash (/).
- In the returned result of each recursion, **ListVersionsResult.getVersions** includes the versioning objects in the folder and **ListVersionsResult.getCommonPrefixes** includes the sub-folders in the folder.

10.8 Object Version ACL

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Setting an ACL for an Object Version

You can call **ObsClient.setObjectAcl** to pass the version ID (**versionId**) to set the ACL for an object version. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Set the object version ACL to public read by specifying a pre-defined ACL.
obsClient.setObjectAcl("bucketname", "objectname", AccessControlList.REST_CANNED_PUBLIC_READ, "versionid");

AccessControlList acl = new AccessControlList();
Owner owner = new Owner();
owner.setId("ownerid");
acl.setOwner(owner);
// Grant the READ permission to all users.
acl.grantPermission(GroupGrantee.ALL_USERS, Permission.PERMISSION_READ);
// Set the ACL for the object version.
obsClient.setObjectAcl("bucketname", "objectname", acl, "versionid");
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

The owner or grantee ID needed in the ACL indicates the account ID, which can be viewed on the **My Credentials** page of OBS Console.

Obtaining the ACL of an Object Version

You can call **ObsClient.getObjectAcl** to pass the version ID (**versionId**) to obtain the ACL of an object version. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

AccessControlList acl = obsClient.getObjectAcl("bucketname", "objectname", "versionid");
System.out.println(acl);
```

10.9 Deleting Versioning Objects

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Deleting a Single Versioning Object

You can call **ObsClient.deleteObject** to pass a version ID (**versionId**) to delete an object version.

This example deletes object **objectname** from bucket **bucketname** by specifying **VersionId**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
obsClient.deleteObject("bucketname", "objectname", "versionid");
```

 Copyright © Huawei Technologies Co., Ltd.

Deleting Versioning Objects in a Batch

You can call **ObsClient.deleteObjects** to batch delete specific versions of an object by passing the **versionId** value of each version to delete.

This example deletes objects **objectname1**, **objectname2**, and **objectname3** from bucket **bucketname** in a batch by specifying their version IDs.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

DeleteObjectsRequest request = new DeleteObjectsRequest("bucketname");
request.setQuiet(false);
List<KeyAndVersion> toDelete = new ArrayList<KeyAndVersion>();
toDelete.add(new KeyAndVersion("objectname1", "versionid1"));
toDelete.add(new KeyAndVersion("objectname2", "versionid2"));
toDelete.add(new KeyAndVersion("objectname3", "versionid3"));
request.setKeyAndVersions(toDelete.toArray(new KeyAndVersion[toDelete.size()]));
DeleteObjectsResult result = obsClient.deleteObjects(request);

Log.i("DeleteObjects","\t" + result.getDeletedObjectResults());
Log.i("DeleteObjects","\t" + result.getErrorResults());
```

 Copyright © Huawei Technologies Co., Ltd.

11 Lifecycle Management

11.1 Lifecycle Management Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS allows you to set lifecycle rules for buckets to automatically transition the storage class of an object and delete expired objects, to effectively use storage features and optimize the storage space. You can set multiple lifecycle rules based on the prefix. A lifecycle rule must contain:

- Rule ID, which uniquely identifies the rule
- Prefix of objects that are under the control of this rule
- Transition policy of an object of the latest version, which can be specified in either mode:
  a. How many days after the object is created
  b. Transition date
- Expiration time of an object of the latest version, which can be specified in either mode:
  a. How many days after the object is created
  b. Expiration date
- Transition policy of a noncurrent object version, which can be specified in the following mode:
  – How many days after the object becomes a noncurrent object version
- Expiration time of a noncurrent object version, which can be specified in the following mode:
  – How many days after the object becomes a noncurrent object version
- Identifier specifying whether the setting is effective

 Copyright © Huawei Technologies Co., Ltd.

For more information, see **Lifecycle Management**.

NOTE

- An object will be automatically deleted by the OBS server once it expires.
- The time set in the transition policy of an object must be earlier than its expiration time, and the time set in the transition policy of a noncurrent object version must be earlier than its expiration time.
- The configured expiration time and transition policy for a noncurrent object version will take effect only when the versioning is enabled or suspended for a bucket.

11.2 Setting Lifecycle Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.setBucketLifecycle** to set lifecycle rules for a bucket.

Setting an Object Transition Policy

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

LifecycleConfiguration config = new LifecycleConfiguration();
LifecycleConfiguration.Rule rule = config.new Rule();
rule.setEnabled(true);
rule.setId("rule1");
rule.setPrefix("prefix");
LifecycleConfiguration.Transition transition = config.new Transition();
// Specify that objects whose names contain the specified prefix will be transitioned 30 days after creation.
transition.setDays(30);
// Specify the storage class of the objects after transition.
transition.setObjectStorageClass(StorageClassEnum.STANDARD);
// Specify when the objects whose names contain the specified prefix will be transitioned.
// transition.setDate(new SimpleDateFormat("yyyy-MM-dd").parse("2018-10-31"));
rule.getTransitions().add(transition);

LifecycleConfiguration.NoncurrentVersionTransition noncurrentVersionTransition = config.new NoncurrentVersionTransition();
// Specify that objects whose names contain the specified prefix will be transitioned 30 days after becoming noncurrent versions.
noncurrentVersionTransition.setDays(30);
// Specify the storage class of the noncurrent object version after transition.
noncurrentVersionTransition.setObjectStorageClass(StorageClassEnum.COLD);
```

 Copyright © Huawei Technologies Co., Ltd.

```
rule.getNoncurrentVersionTransitions().add(noncurrentVersionTransition);

config.addRule(rule);

obsClient.setBucketLifecycle("bucketname", config);
```

Setting an Object Expiration Time

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

LifecycleConfiguration config = new LifecycleConfiguration();

Rule rule = config.new Rule();
rule.setEnabled(true);
rule.setId("rule1");
rule.setPrefix("prefix");
Expiration expiration = config.new Expiration();
// Specify that objects whose names contain the specified prefix will expire 60 days after creation.
expiration.setDays(60);
// Specify the date when the objects whose names contain the specified prefix will expire.
// expiration.setDate(new SimpleDateFormat("yyyy-MM-dd").parse("2018-12-31"));
rule.setExpiration(expiration);

NoncurrentVersionExpiration noncurrentVersionExpiration = config.new NoncurrentVersionExpiration();
// Specify that objects whose names contain the prefix will expire 60 days after changing into noncurrent versions.
noncurrentVersionExpiration.setDays(60);
rule.setNoncurrentVersionExpiration(noncurrentVersionExpiration);
config.addRule(rule);

obsClient.setBucketLifecycle("bucketname", config);
```

11.3 Viewing Lifecycle Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketLifecycle** to view lifecycle rules of a bucket.

This example views the lifecycle configuration of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID
```

 Copyright © Huawei Technologies Co., Ltd.

```
and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

LifecycleConfiguration config = obsClient.getBucketLifecycle("bucketname");

for (LifecycleConfiguration.Rule rule : config.getRules()) {
    Log.i("GetBucketLifecycleConfiguration",rule.getId());
    Log.i("GetBucketLifecycleConfiguration",rule.getPrefix());
    for(LifecycleConfiguration.Transition transition : rule.getTransitions()){
        Log.i("GetBucketLifecycleConfiguration",String.valueOf(transition.getDays()));
        Log.i("GetBucketLifecycleConfiguration",transition.getStorageClass());
    }
    Log.i("GetBucketLifecycleConfiguration",rule.getExpiration() != null ?
String.valueOf(rule.getExpiration().getDays()) : "");
    for(LifecycleConfiguration.NoncurrentVersionTransition noncurrentVersionTransition :
rule.getNoncurrentVersionTransitions()){
        Log.i("GetBucketLifecycleConfiguration",String.valueOf(noncurrentVersionTransition.getDays()));
        Log.i("GetBucketLifecycleConfiguration",noncurrentVersionTransition.getStorageClass());
    }
    Log.i("GetBucketLifecycleConfiguration",rule.getNoncurrentVersionExpiration() != null ?
String.valueOf(rule.getNoncurrentVersionExpiration().getDays()) : "");
}
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

11.4 Deleting Lifecycle Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.deleteBucketLifecycle** to delete lifecycle rules of a bucket.

This example deletes the lifecycle configuration of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

obsClient.deleteBucketLifecycle("bucketname");
```

 Copyright © Huawei Technologies Co., Ltd.

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

12 CORS

12.1 CORS Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Cross-origin access refers to access between different domains. Restricting cross-origin access is a browser policy for security purposes, that is, the same-origin policy.

Due to this same-origin policy, JavaScript in origin A cannot operate objects in origin B or C.

The same-origin policy requires the protocols, domain names (or IP addresses), and ports are all the same. If the protocols, domain names, and ports (if specified) of the two web pages are the same, the two web pages are in the same origin.

CORS allows web application programs in one origin to access resources in another. OBS provides developers with APIs for facilitating cross-origin resource access.

For more information, see **CORS**.

12.2 Setting CORS Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

 Copyright © Huawei Technologies Co., Ltd.

You can call **ObsClient.setBucketCors** to set CORS rules for a bucket. If the bucket is configured with CORS rules, the newly set ones will overwrite the existing ones.

This example sets a CORS rule for bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketCors cors = new BucketCors();

List<BucketCorsRule> rules = new ArrayList<BucketCorsRule>();
BucketCorsRule rule = new BucketCorsRule();

ArrayList<String> allowedOrigin = new ArrayList<String>();
// Specify the origin of the cross-domain request.
allowedOrigin.add( "http://www.a.com");
allowedOrigin.add( "http://www.b.com");
rule.setAllowedOrigin(allowedOrigin);

ArrayList<String> allowedMethod = new ArrayList<String>();
// Specify the request method, which can be GET, PUT, DELETE, POST, or HEAD.
allowedMethod.add("GET");
allowedMethod.add("HEAD");
allowedMethod.add("PUT");
rule.setAllowedMethod(allowedMethod);

ArrayList<String> allowedHeader = new ArrayList<String>();
// Specify whether headers specified in Access-Control-Request-Headers in the OPTIONS request can be used.
allowedHeader.add("x-obs-header");
rule.setAllowedHeader(allowedHeader);

ArrayList<String> exposeHeader = new ArrayList<String>();
// Specify response headers that users can access using application programs.
exposeHeader.add("x-obs-expose-header");
rule.setExposeHeader(exposeHeader);

// Specify the browser's cache time of the returned results of OPTIONS requests for specific resources, in seconds.
rule.setMaxAgeSecond(10);
rules.add(rule);
cors.setRules(rules);

obsClient.setBucketCors("bucketname", cors);
```

NOTE

- **AllowedOrigins** and **AllowedHeaders** respectively can contain up to one wildcard character (*). The wildcard character (*) indicates that all origins or headers are allowed.

 Copyright © Huawei Technologies Co., Ltd.

12.3 Viewing CORS Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketCors** to view CORS rules of a bucket.

This example views the CORS rule of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);


BucketCors cors = obsClient.getBucketCors("bucketname");
for(BucketCorsRule rule : cors.getRules()){
    Log.i("GetBucketCors","\t" + rule.getId());
    Log.i("GetBucketCors","\t" + rule.getMaxAgeSecond());
    Log.i("GetBucketCors","\t" + rule.getAllowedHeader());
    Log.i("GetBucketCors","\t" + rule.getAllowedOrigin());
    Log.i("GetBucketCors","\t" + rule.getAllowedMethod());
    Log.i("GetBucketCors","\t" + rule.getExposeHeader());
}
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

12.4 Deleting CORS Rules

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.deleteBucketCors** to delete CORS rules of a bucket.

This example deletes the CORS rule of bucket **bucketname**.

The example code is as follows:

 Copyright © Huawei Technologies Co., Ltd.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

obsClient.deleteBucketCors("bucketname");
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

13 Access Logging

13.1 Logging Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS allows you to configure access logging for buckets. After the configuration, access to buckets will be recorded in the format of logs. These logs will be saved in specific buckets in OBS.

You can enable OBS logging for bucket analysis or audit purposes. With access logs, a bucket owner can analyze the characteristics, types, or trends of requests sent to the bucket.

With logging enabled, OBS automatically logs access requests for the bucket and writes the generated log files into a specified bucket.

You need to specify a bucket for storing log files when enabling logging for a bucket. Log files can be stored in any bucket you own in the region where the logged bucket is, including the logged bucket itself.

For more information, see **Logging**.

13.2 Enabling Bucket Logging

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

 Copyright © Huawei Technologies Co., Ltd.

You can call **ObsClient.setBucketLogging** to enable bucket logging.

NOTICE

The source bucket and target bucket of logging must be in the same region.

NOTE

If the bucket is in the OBS Infrequent Access or Archive storage class, it cannot be used as the target bucket.

Enabling Bucket Logging

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketLoggingConfiguration config = new BucketLoggingConfiguration();
// Set an agency. You need to create one on IAM.
config.setAgency("your agency");
config.setTargetBucketName("targetbucketname");
config.setLogfilePrefix("targetprefix");

obsClient.setBucketLogging("bucketname", config);
```

Setting ACLs for Objects to Be Logged

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

String targetBucket = "targetbucketname";

// Configure logging.
BucketLoggingConfiguration config = new BucketLoggingConfiguration();
// Set an agency. You need to create one on IAM.
config.setAgency("your agency");
config.setTargetBucketName(targetBucket);
config.setLogfilePrefix("prefix");

// Grant the READ permission on the objects to be logged to all users.
GrantAndPermission grant1 = new GrantAndPermission(GroupGrantee.ALL_USERS,
```

 Copyright © Huawei Technologies Co., Ltd.

```
Permission.PERMISSION_READ);
config.setTargetGrants(new GrantAndPermission[]{grant1});

obsClient.setBucketLogging("bucketname", config);
```

13.3 Viewing Bucket Logging

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketLogging** to view the logging settings of a bucket.

This example views the logging configuration of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketLoggingConfiguration config = obsClient.getBucketLogging("bucketname");
Log.i("GetBucketLoggingConfiguration","\t" + config.getTargetBucketName());
Log.i("GetBucketLoggingConfiguration","\t" + config.getLogfilePrefix());
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

13.4 Disabling Bucket Logging

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

To disable logging for a bucket is to call **ObsClient.setBucketLogging** to delete the logging configuration.

This example disables logging for bucket **bucketname**.

The example code is as follows:

 Copyright © Huawei Technologies Co., Ltd.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Leave the logging settings in blank.
obsClient.setBucketLogging("bucketname", new BucketLoggingConfiguration());
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

14 Static Website Hosting

14.1 Static Website Hosting Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Static websites typically only contain static web pages and some scripts that can run on clients (such as JavaScript and Flash). In contrast, dynamic websites depend on scripts that need to be processed on the server side, including PHP, JSP, and ASP.Net.

To host your static website on OBS, you can upload static website files to your bucket as objects, configure the public read permission for the objects, and then configure static website hosting for your bucket.

After this, when third-party users access your websites, they actually access the objects in your bucket in OBS.

When using static website hosting, you can configure request redirection to redirect specific or all requests.

For more information, see **Static Website Hosting**.

14.2 Website File Hosting

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

 Copyright © Huawei Technologies Co., Ltd.

You can perform the following to implement website file hosting:

Step 1 Upload a website file to your bucket in OBS as an object and set the MIME type for the object.

Step 2 Set the object ACL to public read.

Step 3 Access the object using a browser.

----End

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Upload objects and set the MIME type for the objects.
PutObjectRequest request = new PutObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("test.html");
request.setFile(new File("localfile.html"));
ObjectMetadata metadata = new ObjectMetadata();
metadata.setContentType("text/html");
request.setMetadata(metadata);
obsClient.putObject(request);

// Set the ACL of the object to public read.
obsClient.setObjectAcl("bucketname", "test.html", AccessControlList.REST_CANNED_PUBLIC_READ);
```

NOTE

You can use **https://***bucketname.your-endpoint***/test.html** in a browser to access files hosted using the sample code.

14.3 Setting Website Hosting

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.setBucketWebsite** to set website hosting for a bucket.

Configuring the Default Homepage and Error Pages

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

WebsiteConfiguration config = new WebsiteConfiguration();
// Configure the default homepage.
config.setSuffix("index.html");
// Configure the error pages.
config.setKey("error.html");
obsClient.setBucketWebsite("bucketname", config);
```

Configuring the Redirection Rules

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

WebsiteConfiguration config = new WebsiteConfiguration();
// Configure the default homepage.
config.setSuffix("index.html");
// Configure the error pages.
config.setKey("error.html");

RouteRule rule = new RouteRule();
Redirect r = new Redirect();
r.setHostName("www.example.com");
r.setHttpRedirectCode("305");
r.setRedirectProtocol(ProtocolEnum.HTTP);
r.setReplaceKeyPrefixWith("replacekeyprefix");
rule.setRedirect(r);
RouteRuleCondition condition = new RouteRuleCondition();
condition.setHttpErrorCodeReturnedEquals("404");
condition.setKeyPrefixEquals("keyprefix");
rule.setCondition(condition);
config.getRouteRules().add(rule);

obsClient.setBucketWebsite("bucketname", config);
```

Configuring Redirection for All Requests

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
```

 Copyright © Huawei Technologies Co., Ltd.

```
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

WebsiteConfiguration config = new WebsiteConfiguration();
RedirectAllRequest redirectAll = new RedirectAllRequest();
redirectAll.setHostName("www.example.com");
// Configure the support for both HTTP and HTTPS.
redirectAll.setRedirectProtocol(ProtocolEnum.HTTP);
config.setRedirectAllRequestsTo(redirectAll);

obsClient.setBucketWebsite("bucketname", config);
```

14.4 Viewing Website Hosting Settings

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketWebsite** to view the hosting settings of a bucket.

This example views the hosting configuration of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

WebsiteConfiguration config = obsClient.getBucketWebsite("bucketname");
Log.i("GetBucketWebsiteConfiguration", "\t" + config.getKey());
Log.i("GetBucketWebsiteConfiguration", "\t" + config.getSuffix());
for(RouteRule rule : config.getRouteRules()){
    Log.i("GetBucketWebsiteConfiguration", "\t" + rule);
}
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

14.5 Deleting Website Hosting Settings

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.deleteBucketWebsite** to delete the hosting settings of a bucket.

This example deletes the hosting configuration of bucket **bucketname**.

The example code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

obsClient.deleteBucketWebsite("bucketname");
```

NOTE

- To handle the error codes possibly returned during the operation, see **OBS Server-Side Error Codes**.

 Copyright © Huawei Technologies Co., Ltd.

15 Tag Management

15.1 Tagging Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Tags are used to identify and classify OBS buckets.

15.2 Setting Bucket Tags

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.setBucketTagging** to set bucket tags. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";

// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
```

 Copyright © Huawei Technologies Co., Ltd.

```
BucketTagInfo bucketTagInfo = new BucketTagInfo();

TagSet tagSet = new TagSet();

tagSet.addTag("tag1", "value1");
tagSet.addTag("tag2", "value2");

bucketTagInfo.setTagSet(tagSet);
obsClient.setBucketTagging("bucketname", bucketTagInfo);
```

NOTE

- A bucket can have up to 10 tags.
- The key and value of a tag can be composed of Unicode characters.

15.3 Viewing Bucket Tags

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.getBucketTagging** to view bucket tags. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

BucketTagInfo bucketTagInfo = obsClient.getBucketTagging("bucketname");
for(Tag tag : bucketTagInfo.getTagSet().getTags()){
    Log.i("GetBucketTagging", "\t" + tag.getKey() + ":" + tag.getValue());
}
```

15.4 Deleting Bucket Tags

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

You can call **ObsClient.deleteBucketTagging** to delete bucket tags. Sample code is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables
```

 Copyright © Huawei Technologies Co., Ltd.

```
for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID
and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/
intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

obsClient.deleteBucketTagging("bucketname");
```

 Copyright © Huawei Technologies Co., Ltd.

16 Server-Side Encryption

16.1 Server-Side Encryption Overview

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

OBS supports server-side encryption.

For more information, see **Server-Side Encryption**.

16.2 Encryption Description

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

The following table lists APIs related to server-side encryption:

Method in OBS Android SDK	Description	Supported Encryption Type
ObsClient.putObject	Sets the encryption algorithm and key during object upload to enable server-side encryption.	SSE-KMS SSE-C

 Copyright © Huawei Technologies Co., Ltd.

Method in OBS Android SDK	Description	Supported Encryption Type
ObsClient.getObject	Sets the decryption algorithm and key during object download to decrypt the object.	SSE-C
ObsClient.copyObject	1. Sets the decryption algorithm and key for decrypting the source object during object copy. 2. Sets the encryption algorithm and key during object copy to enable the encryption algorithm for the target object.	SSE-KMS SSE-C
ObsClient.getObjectMetadata	Sets the decryption algorithm and key when obtaining the object metadata to decrypt the object.	SSE-C
ObsClient.initiateMultipartUpload	Sets the encryption algorithm and key when initializing a multipart upload to enable server-side encryption for the final object generated.	SSE-KMS SSE-C
ObsClient.uploadPart	Sets the encryption algorithm and key during multipart upload to enable server-side encryption for parts.	SSE-C
ObsClient.copyPart	1. Sets the decryption algorithm and key for decrypting the source object during multipart copy. 2. Sets the encryption algorithm and key during multipart copy to enable the encryption algorithm for the target part.	SSE-C

16.3 Example of Encryption

NOTICE

If you have any questions during development, post them on the **Issues** page of GitHub. For details about parameters and usage of each API, see the **API Reference**.

Encrypting an Object to Be Uploaded

Sample code:

 Copyright © Huawei Technologies Co., Ltd.

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

PutObjectRequest request = new PutObjectRequest();
request.setBucketName("bucketname");
request.setObjectKey("objectname");
request.setFile(new File("localfile"));
// Set the SSE-C encryption algorithm.
SseCHeader sseCHeader = new SseCHeader();
sseCHeader.setAlgorithm(ServerAlgorithm.AES256);
// Set the key used to encrypt and decrypt objects in SSE-C mode. This value is a Base64-encoded key.
sseCHeader.setSseCKeyBase64("your base64 sse-c key generated by AES-256 algorithm");

request.setSseCHeader(sseCHeader);
obsClient.putObject(request);
```

Decrypting a Downloaded Object

Sample code:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an ObsClient instance.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);

GetObjectRequest request = new GetObjectRequest("bucketname", "objectname");
// Set the decryption algorithm to SSE-C.
SseCHeader sseCHeader = new SseCHeader();
sseCHeader.setAlgorithm(ServerAlgorithm.AES256);
// The key used here must be the one used for uploading the object.
sseCHeader.setSseCKeyBase64("your base64 sse-c key generated by AES-256 algorithm");

request.setSseCHeader(sseCHeader);
ObsObject obsObject = obsClient.getObject(request);

obsObject.getObjectContent().close();
```

 Copyright © Huawei Technologies Co., Ltd.

17 Troubleshooting

17.1 OBS Server-Side Error Codes

If the OBS server encounters an error when processing a request, a response containing the error code and error description is returned. The following table lists details about each error code and HTTP status code.

Error Code	Description	HTTP Status Code
AccessDenied	Access denied.	403 Forbidden
AccessForbidden	Insufficient permission.	403 Forbidden
AccountProblem	Your account is abnormal (for example, being expired or frozen).	403 Forbidden
AllAccessDisabled	You have no permission to perform the operation.	403 Forbidden
AmbiguousGrantByEmailAddress	The provided email address is associated with more than one account.	400 Bad Request
BadDigest	The specified value of **Content-MD5** does not match the value received by OBS.	400 Bad Request
BadDomainName	Invalid domain name.	400 Bad Request
BadRequest	Invalid request parameters.	400 Bad Request

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
BucketAlreadyExists	The requested bucket name already exists. The bucket namespace is shared by all users of OBS. Try again with another bucket name.	409 Conflict
BucketAlreadyOwnedByYou	Your previous request for creating the named bucket succeeded and you already own it.	409 Conflict
BucketNotEmpty	The bucket that you tried to delete is not empty.	409 Conflict
CredentialsNotSupported	This request does not support security credentials.	400 Bad Request
CustomDomainAreadyExist	The configured domain already exists.	400 Bad Request
CustomDomainNotExist	The domain to be operated does not exist.	400 Bad Request
DeregisterUserId	The user has been deregistered.	403 Forbidden
EntityTooSmall	The size of the object to upload is smaller than the lower limit.	400 Bad Request
EntityTooLarge	The size of the object to upload is larger than the upper limit.	400 Bad Request
FrozenUserId	The user has been frozen.	403 Forbidden
IllegalVersioningConfigurationException	Invalid versioning configuration in the request.	400 Bad Request
IllegalLocationConstraintException	The configured region limitation is inconsistent with the region where it resides.	400 Bad Request
InArrearOrInsufficientBalance	The user has no permission to perform some operations due to being in arrears or insufficient balance.	403 Forbidden

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
IncompleteBody	Incomplete request body.	400 Bad Request
IncorrectNumberOfFilesInPostRequest	Each POST request must contain one file to upload.	400 Bad Request
InlineDataTooLarge	The length of inline data exceeds the upper limit.	400 Bad Request
InsufficientStorageSpace	Insufficient storage space.	403 Forbidden
InternalError	Internal error. Please try again later.	500 Internal Server Error
InvalidAccessKeyId	The access key ID provided by the customer does not exist in the system.	403 Forbidden
InvalidAddressingHeader	The anonymous role must be specified.	N/A
InvalidArgument	Invalid parameter.	400 Bad Request
InvalidBucketName	The specified bucket name in the request is invalid.	400 Bad Request
InvalidBucket	The bucket to be accessed does not exist.	400 Bad Request
InvalidBucketState	Invalid bucket status.	409 Conflict
InvalidBucketStoragePolicy	An invalid new policy is specified during bucket policy modification.	400 Bad Request
InvalidDigest	The **Content-MD5** value specified in the HTTP header is invalid.	400 Bad Request
InvalidEncryptionAlgorithmError	Incorrect encryption algorithm.	400 Bad Request
InvalidLocationConstraint	The location specified during bucket creation is invalid.	400 Bad Request
InvalidPart	One or more specified parts are not found. The parts may not be uploaded or the specified entity tags (ETags) do not match the parts' ETags.	400 Bad Request

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
InvalidPartOrder	Parts are not listed in ascending order by part number.	400 Bad Request
InvalidPayer	All access to this object has been disabled.	403 Forbidden
InvalidPolicyDocument	The content of the form does not meet the conditions specified in the policy document.	400 Bad Request
InvalidRange	The requested range cannot be obtained.	416 Client Requested Range Not Satisfiable
InvalidRedirectLocation	Invalid redirect location.	400 Bad Request
InvalidRequest	Invalid request.	400 Bad Request
InvalidRequestBody	Invalid POST request body.	400 Bad Request
InvalidSecurity	Invalid security credentials.	403 Forbidden
InvalidStorageClass	Invalid storage class.	400 Bad Request
InvalidTargetBucketForLogging	The delivery group has no ACL permission for the target bucket.	400 Bad Request
InvalidURI	The specified URI cannot be resolved.	400 Bad Request
KeyTooLong	The provided key is too long.	400 Bad Request
MalformedACLError	The provided XML file has syntax errors or does not meet the format requirements.	400 Bad Request
MalformedError	The XML format in the request is incorrect.	400 Bad Request
MalformedLoggingStatus	The XML format of **Logging** is incorrect.	400 Bad Request
MalformedPolicy	The bucket policy does not pass.	400 Bad Request

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
MalformedPOSTRequest	The body of the POST request is in an incorrect format.	400 Bad Request
MalformedQuotaError	The Quota XML format is incorrect.	400 Bad Request
MalformedXML	This error code is returned after you send an XML file in incorrect format. The error message states: "The XML you provided was not well-formed or did not validate against our published schema."	400 Bad Request
MaxMessageLengthExceeded	The request is too long.	400 Bad Request
MaxPostPreDataLengthExceeded Error	The POST request fields prior to the file to upload are too large.	400 Bad Request
MetadataTooLarge	The size of the metadata header exceeds the upper limit.	400 Bad Request
MethodNotAllowed	The specified method is not allowed against the requested resource. The message "Specified method is not supported." is returned.	405 Method Not Allowed
MissingContentLength	The HTTP header **Content-Length** is not provided.	411 Length Required
MissingRegion	The region information is missing in the request, and the default region is required in the system.	400 Bad Request
MissingRequestBodyError	This error code is returned after you send an empty XML file. The error message states: "Request body is empty."	400 Bad Request
MissingRequiredHeader	Required headers are missing in the request.	400 Bad Request

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
MissingSecurityHeader	A required header is missing in the request.	400 Bad Request
NoSuchBucket	The bucket does not exist.	404 Not Found
NoSuchBucketPolicy	No bucket policy exists.	404 Not Found
NoSuchCORSConfiguration	No CORS configuration exists.	404 Not Found
NoSuchCustomDomain	The requested user domain does not exist.	404 Not Found
NoSuchKey	The key does not exist.	404 Not Found
NoSuchLifecycleConfiguration	The requested lifecycle rule does not exist.	404 Not Found
NoSuchPolicy	The policy name does not exist.	404 Not Found
NoSuchUpload	The multipart upload does not exist. The upload ID does not exist or the multipart upload has been aborted or completed.	404 Not Found
NoSuchVersion	The specified version ID does not match any existing version.	404 Not Found
NoSuchWebsiteConfiguration	The requested website does not exist.	404 Not Found
NotImplemented	The provided header implies a function that is unavailable.	501 Not Implemented
NotSignedUp	Your account is not signed up in the system. Sign up the account before use.	403 Forbidden
OperationAborted	A conflicting operation is being performed on this resource. Try again later.	409 Conflict
PermanentRedirect	The requested bucket has been permanently redirected to a new URL. All future requests must be sent to the new URL.	301 Moved Permanently

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
PreconditionFailed	At least one of the specified preconditions is not met.	412 Precondition Failed
Redirect	The request is temporarily redirected.	307 Moved Temporarily
RequestIsNotMultiPartContent	A bucket POST request must contain an enclosure-type multipart or the form-data.	400 Bad Request
RequestTimeout	No read or write operation has been performed within the timeout period of the socket connection between the user and the server.	400 Bad Request
RequestTimeTooSkewed	The request time and the server's time differ a lot.	403 Forbidden
RequestTorrentOfBucketError	Requesting the bucket's torrent file is not allowed.	400 Bad Request
ServiceNotImplemented	The request method is not implemented by the server.	501 Not Implemented
ServiceNotSupported	The request method is not supported by the server.	409 Conflict
ServiceUnavailable	The server is overloaded or has internal errors.	503 Service Unavailable
SignatureDoesNotMatch	The provided signature does not match the signature calculated by OBS. Check your AK and SK and signature calculation method.	403 Forbidden
SlowDown	Too frequent requests. Reduce your request frequency.	503 Service Unavailable
System Capacity Not enough	Insufficient system space.	403 Forbidden
TooManyCustomDomains	Too many user domains are configured.	400 Bad Request
TemporaryRedirect	The request is redirected to the bucket while the domain name server (DNS) is being updated.	307 Moved Temporarily

 Copyright © Huawei Technologies Co., Ltd.

Error Code	Description	HTTP Status Code
TooManyBuckets	You have attempted to create more buckets than allowed.	400 Bad Request
TooManyObjectCopied	The number of copies of a single object exceeds the upper limit.	400 Bad Request
TooManyWrongSignature	The request is rejected due to high-frequency errors.	400 Bad Request
UnexpectedContent	This request does not support fields with content.	400 Bad Request
UnresolvableGrantByEmailAddress	The provided email address does not match any recorded accounts.	400 Bad Request
UserKeyMustBeSpecified	The user's AK is not carried in the request.	400 Bad Request
WebsiteRedirect	The website request lacks **bucketName**.	301 Moved Permanently
KMS.DisabledException	The master key is disabled in SSE-KMS mode.	400 Bad Request
KMS.NotFoundException	The master key does not exist in SSE-KMS mode.	400 Bad Request
RestoreAlreadyInProgress	The Archive object is being restored. The request conflicts with another one.	409 Conflict
ObjectHasAlreadyRestored	The objects have been restored and the retention period of the objects cannot be shortened.	409 Conflict
InvalidObjectState	The restored object is not an Archive object.	403 Forbidden
InvalidTagError	An invalid tag is provided when configuring the bucket tag.	400 Bad Request
NoSuchTagSet	The specified bucket does not have a tag.	404 Not Found

 Copyright © Huawei Technologies Co., Ltd.

17.2 SDK Custom Exceptions

SDK custom exceptions (**ObsException**), thrown by **ObsClient**, are inherited from class **java.lang.RuntimeException**. Exceptions are usually OBS server errors, including **OBS error codes** and error information. This facilitates users to locate problems and troubleshot faults.

ObsException contains the following error information:

- **ObsException.getResponseCode**: HTTP status code
- **ObsException.getErrorCode**: Error code returned by the OBS server
- **ObsException.getErrorMessage**: Error description returned by the OBS server
- **ObsException.getErrorRequestId**: Request ID returned by the OBS server
- **ObsException.getErrorHostId**: Requested server ID
- **ObsException.getResponseHeaders:** HTTP response headers

17.3 SDK Common Response Headers

After you call an API in an instance of **ObsClient**, an instance of the **HeaderResponse** class (or of its sub-class) will be returned. It contains information about HTTP/HTTPS response headers.

Sample code for processing public response headers:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Create an instance of ObsClient.
ObsClient obsClient = new ObsClient(ak, sk, endPoint);
HeaderResponse response = obsClient.createBucket("bucketname");

// Obtain the UUID from the public response headers.
Log.i("CreateBucket", "\t" + response.getRequestId());

obsClient.close();
```

17.4 Log Analysis

Log Path

The log path of the OBS Android SDK is specified using **LogConfigurator.setLogFileDir**. Logs are saved in the **logs** directory of the SD card by default. The log file name is **OBS-SDK.log**.

 Copyright © Huawei Technologies Co., Ltd.

Log Format

The SDK log format is: Log time|thread ID|log level|log content. The following are examples:

```
2017-08-21 17:40:07 133|main|INFO |HttpClient cost 157 ms to apply http request
2017-08-21 17:40:07 133|main|INFO |Received expected response code: true
2017-08-21 17:40:07 133|main|INFO |expected code(s): [200, 204].

2017-08-21 17:40:06 820|main|INFO |Storage|1|HTTP+XML|ObsClient||||2017-08-21 17:40:05|2017-08-21 17:40:06|||0|
2017-08-21 17:40:07 136|main|INFO |Storage|1|HTTP+XML|setObjectAcl||||2017-08-21 17:40:06|2017-08-21 17:40:07|||0|
2017-08-21 17:40:07 137|main|INFO |ObsClient [setObjectAcl] cost 312 ms
```

Log Level

When current logs cannot be used to troubleshoot system faults, you can change the log level to obtain more information. You can obtain the most information in **TRACE** logs and the least information in **ERROR** logs. You can call **LogConfigurator.setLogLevel** to set bucket tags.

The following table describes each log level in detail.

Log Level	Description	Value in OBS Android SDK
OFF	Close level. If this level is set, logging will be disabled.	LogConfigurator.OFF
TRACE	Trace level. If this level is set, all log information will be printed. This level is not recommended.	LogConfigurator.TRACE
DEBUG	Debugging level. If this level is set, information about logs of the **INFO** level and above, HTTP/HTTPS request and response headers, and **StringToSign** information calculated by authentication algorithm will be printed.	LogConfigurator.DEBUG
INFO	Information level. If this level is set, information about logs of the **WARN** level and above, time consumed for each HTTP/HTTPS request, and time consumed for calling the **ObsClient** API will be printed.	LogConfigurator.INFO
WARN	Warning level. If this level is set, information about logs of the **ERROR** level and above, as well as information about some critical events (for example, the number of retry attempts exceeds the upper limit) will be printed.	LogConfigurator.WARN
ERROR	Error level. If this level is set, only error information will be printed.	LogConfigurator.ERROR

 Copyright © Huawei Technologies Co., Ltd.

Log File Cannot Be Generated

If logs cannot be generated, check whether the following permissions are added in **AndroidManifest.xml**:

```
<uses-permission android:name="android.permission.READ_EXTERNAL_STORAGE" />
<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />
```

17.5 Lack of Classes

If an error indicating the lack of a class is displayed when you are using OBS Android SDK for secondary development, ensure that the following dependencies are saved in the **libs** directory, in addition to package **esdk-obs-java-*x.x.x*.jar**:

- java-xmlbuilder-1.3.jar
- okhttp-4.8.0.jar
- okio-2.7.0.jar

17.6 Connection Timeout

If the error code obtained by calling **ObsException.getResponseCode** is 408, the connection to OBS timed out.

The possible causes are as follows:

1. The service address (Endpoint) is incorrect or the network is disconnected. In this case, check the service address and network status.

2. The network delay between the client and the OBS server is too long. Check the health status of the network between the client and the OBS server.

17.7 Resources Cannot Be Released

If memory leakage occurs or the OBS server is not disconnected after the OBS Android SDK is used, perform the following operations:

1. Check whether **ObsClient.close** is correctly called.

2. Check whether **ObsObject.getObjectContent.close** is correctly called to release resources.

17.8 Unmatched Signatures

The HTTP status code obtained from **ObsException** is 403, and the OBS server-side error is **SignatureDoesNotMatch**.

The possible causes are as follows:

1. The SK passed during ObsClient initialization is incorrect. Ensure that the SK is correct.
2. This is a bug in the OBS Android SDK of an earlier version. Upgrade the SDK to the latest version.

 Copyright © Huawei Technologies Co., Ltd.

3. The endpoint passed during ObsClient initialization is incorrect. Ensure that the endpoint is correct.

17.9 NetworkOnMainThreadException

Error "NetworkOnMainThreadException" usually occurs when a network request is in the MainThread class.

Cause:

In Android 3.0 and later versions, the program cannot access the network in the main thread. Network access requests must be placed in separate threads.

Solution:

1. To prevent network access requests from blocking the main thread, place such requests in separate threads or handle them asynchronously with AsyncTask.

2. To avoid this problem, it is recommended that time-consuming network requests be placed in a sub-thread. Then, use the handler to communicate with the main thread.

 Copyright © Huawei Technologies Co., Ltd.

18 FAQ

18.1 Does the SDK Support Uploading, Downloading, or Copying Objects in a Batch?

No.

Currently, the SDK does not provide such APIs. You need to encapsulate the service codes for uploading, downloading, or copying objects in a batch by yourself. The procedure is as follows:

Step 1 Invoke **listObjects** to list all objects to be uploaded, downloaded, or copied. For details about the code example, see **Listing Objects**.

Step 2 Invokes the API for uploading, downloading, or copying a single object for the listed objects.

----End

The example code for uploading objects in a batch is as follows:

```
// Hard-coded or plaintext AK/SK are risky. For security purposes, encrypt your AK/SK and store them in the configuration file or environment variables. In this example, the AK/SK are stored in environment variables for identity authentication. Before running this example, configure environment variables ACCESS_KEY_ID and SECRET_ACCESS_KEY_ID.
// Obtain an AK/SK pair on the management console. For details, see https://support.huaweicloud.com/intl/en-us/usermanual-ca/ca_01_0003.html.
String ak = System.getenv("ACCESS_KEY_ID");
String sk = System.getenv("SECRET_ACCESS_KEY_ID");
String endPoint = "https://your-endpoint";
// Define the prefix of objects in a bucket.
final String objectPre = "object/";
// Folder to be uploaded. An example of the folder path is /storage/emulated/0/Pictures. Ensure that the files to be uploaded in the folder meet expectations.
// Example of obtaining the path: final String localDirPath = Environment.getExternalStorageDirectory().getAbsolutePath() + "/Picture";
final String localDirPath = Environment.getExternalStorageDirectory().getAbsolutePath() + "localDirPath";

final List<File> list = new ArrayList<>();

public void uploadFiles() {
// Traverse the folder to be uploaded and obtain all objects to be uploaded.
    File file = new File(localDirPath);
    listFiles(file);
```

 Copyright © Huawei Technologies Co., Ltd.

```
// Create an ObsClient instance.
    final ObsClient obsClient = new ObsClient(ak, sk, endPoint);

// Initialize the thread pool.
    ExecutorService executorService = Executors.newFixedThreadPool(20);

// Concurrently upload parts.
    for (File f : list) {
        executorService.execute(() -> {
            if (f.isDirectory()) {
            // For empty folders, create empty folder objects in the bucket.
                String remoteObjectKey = objectPre + f.getPath().substring(localDirPath.length() + 1) + "/";
                obsClient.putObject(bucketName, remoteObjectKey, new ByteArrayInputStream(new byte[0]));
            } else {
                String remoteObjectKey = objectPre + f.getPath().substring(localDirPath.length() + 1);
                obsClient.putObject(bucketName, remoteObjectKey, new File(f.getPath()));
            }
        });
    }

// Wait until the upload is complete.
    executorService.shutdown();
    while (!executorService.isTerminated()) {
        try {
            executorService.awaitTermination(5, TimeUnit.SECONDS);
        } catch (InterruptedException e) {
            e.printStackTrace();
        }
    }
// Close obsClient.
    try {
        obsClient.close();
    } catch (IOException e) {
        e.printStackTrace();
    }
}

// Scan all objects in the folder.
void listFiles(File file) {
    File[] fs = file.listFiles();
    assert fs != null;
    if (fs.length < 1) {
        // If uploading an empty folder is required, add it to the list.
        list.add(file);
    } else {
        for (File f : fs) {
            if (f.isDirectory()) {
                listFiles(f);
            }
            if (f.isFile()) {
                // Add objects to be uploaded to the list.
                list.add(f);
            }
        }
    }
}
```

NOTE

You can use multiple threads to concurrently upload, download, and copy data to improve efficiency.

 Copyright © Huawei Technologies Co., Ltd.

A API Reference

For details about all parameters and definitions of APIs in the OBS Android SDK, see the **OBS Android SDK API Reference**.

 Copyright © Huawei Technologies Co., Ltd.